

Symantec NetBackup™ Installation Guide

UNIX and Windows

Release 7.7.1

Symantec NetBackup™ Installation Guide

Documentation version: 7.7.1

PN: 21317387

Legal Notice

Copyright © 2015 Symantec Corporation. All rights reserved.

Symantec, the Symantec Logo, the Checkmark Logo, Veritas, the Veritas Logo, and NetBackup are trademarks or registered trademarks of Symantec Corporation or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Symantec Corporation and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. SYMANTEC CORPORATION SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, "Rights in Commercial Computer Software or Commercial Computer Software Documentation", as applicable, and any successor regulations. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Symantec Corporation
350 Ellis Street
Mountain View, CA 94043

<http://www.symantec.com>

Technical Support

Symantec Technical Support maintains support centers globally. Technical Support's primary role is to respond to specific queries about product features and functionality. The Technical Support group also creates content for our online Knowledge Base. The Technical Support group works collaboratively with the other functional areas within Symantec to answer your questions in a timely fashion. For example, the Technical Support group works with Product Engineering and Symantec Security Response to provide alerting services and virus definition updates.

Symantec's support offerings include the following:

- A range of support options that give you the flexibility to select the right amount of service for any size organization
- Telephone and/or Web-based support that provides rapid response and up-to-the-minute information
- Upgrade assurance that delivers software upgrades
- Global support purchased on a regional business hours or 24 hours a day, 7 days a week basis
- Premium service offerings that include Account Management Services

For information about Symantec's support offerings, you can visit our website at the following URL:

www.symantec.com/business/support/

All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policy.

Contacting Technical Support

Customers with a current support agreement may access Technical Support information at the following URL:

www.symantec.com/business/support/

Before contacting Technical Support, make sure you have satisfied the system requirements that are listed in your product documentation. Also, you should be at the computer on which the problem occurred, in case it is necessary to replicate the problem.

When you contact Technical Support, please have the following information available:

- Product release level
- Hardware information

- Available memory, disk space, and NIC information
- Operating system
- Version and patch level
- Network topology
- Router, gateway, and IP address information
- Problem description:
 - Error messages and log files
 - Troubleshooting that was performed before contacting Symantec
 - Recent software configuration changes and network changes

Licensing and registration

If your Symantec product requires registration or a license key, access our technical support Web page at the following URL:

www.symantec.com/business/support/

Customer service

Customer service information is available at the following URL:

www.symantec.com/business/support/

Customer Service is available to assist with non-technical questions, such as the following types of issues:

- Questions regarding product licensing or serialization
- Product registration updates, such as address or name changes
- General product information (features, language availability, local dealers)
- Latest information about product updates and upgrades
- Information about upgrade assurance and support contracts
- Information about the Symantec Buying Programs
- Advice about Symantec's technical support options
- Nontechnical presales questions
- Issues that are related to CD-ROMs, DVDs, or manuals

Support agreement resources

If you want to contact Symantec regarding an existing support agreement, please contact the support agreement administration team for your region as follows:

Asia-Pacific and Japan customercare_apac@symantec.com

Europe, Middle-East, and Africa semea@symantec.com

North America and Latin America supportsolutions@symantec.com

Contents

Technical Support	3	
Chapter 1	Preparing for installation	10
	Restrictions on the NetBackup installation directory	10
	About compatibility between NetBackup versions	11
	About Symantec Operations Readiness Tools	11
	Recommended SORT procedures for new installations	12
	Recommended SORT procedures for upgrades	16
	About NetBackup software availability	18
	About the NetBackup media kit	18
	About the NetBackup Electronic Software Distribution (ESD) images	19
	About storage device configuration	20
	Locating supported robot types	21
	How to install NetBackup	21
	About the NetBackup preinstall checker	22
	About the NetBackup Product Improvement Program	23
	About security certificates for NetBackup media servers	23
Chapter 2	NetBackup licenses	25
	About NetBackup license key requirements	25
	About NetBackup license compatibility	26
	About license key entry	26
	Frequently asked questions about license keys	28
Chapter 3	Installing server software on UNIX systems	32
	About NetBackup server installation requirements for UNIX/Linux systems	32
	Do not mix non-English versions of Windows and UNIX platforms unless master and media servers are NetBackup appliances	34
	NetBackup installations on environments that run different versions of UNIX-based operating systems	34
	Special installation guidelines for Solaris systems	35

	Special installation guidelines for HP-UX systems	35
	Special installation guidelines for UNIX clustered environments	35
	How the installation script works	36
	About mounting the NetBackup software media	37
	Mounting NetBackup software media on UNIX or Linux systems	38
	Installing NetBackup master server software on UNIX	39
	Continuing with NetBackup software installation	45
	Installing NetBackup media server software on UNIX	45
	About pushing client software from a master server to clients	49
	Installing client type software on a master server	50
	Installing NetBackup add-on products	51
	How to configure the window manager for the Java Interface (NetBackup-Java compatible platforms)	51
Chapter 4	Installing server software on Windows systems	53
	Requirements for Windows NetBackup server installation	53
	About the NetBackup preinstallation Environment Checker	56
	Running the preinstallation Environment Checker	57
	Requirements for Windows cluster installations and upgrades	59
	Performing local, remote, or clustered server installation on Windows systems	61
	Post-installation tasks for NetBackup cluster environments	74
	Verifying Windows cluster installations or upgrades	74
	Installing NetBackup servers silently on Windows systems	75
Chapter 5	Installing administrative interface	78
	About the NetBackup Remote Administration Console	78
	Installing the NetBackup Remote Administration Console	78
	Configuring server lists for the NetBackup Remote Administration Console	80
	Adding remote servers to administer from an existing NetBackup Remote Administration Console	81
	About the NetBackup Administration Console	82
	Installing the NetBackup Java Administration Console	82
	Installing or removing multiple versions of the NetBackup-Java Administration Console on Windows	83
	Installing multiple versions of the NetBackup-Java Administration Console on Windows	83
	Removing earlier versions of the NetBackup-Java Administration Console on Windows	84

Chapter 6	Installing NetBackup client software	85
	About NetBackup client installation	85
	About NetBackup client installation on Windows	86
	About Windows client installation methods and requirements	86
	Installing NetBackup Windows clients locally or remotely	89
	Installing NetBackup Windows clients silently	95
	How to configure NetBackup clients	96
	About NetBackup client installation on UNIX/Linux	97
	About UNIX/Linux client installation methods	99
	Installing UNIX clients locally	100
	About remote installation methods for UNIX/Linux clients	102
	Adding a UNIX/Linux client after initial server installation	108
	Upgrading clients after servers are upgraded	110
Chapter 7	Configuring NetBackup	114
	About NetBackup startup and shutdown scripts	114
	About NetBackup server configuration	116
	Starting the NetBackup Administration Console	118
	About the Device Configuration Wizard	119
	About the Volume Configuration Wizard	121
	About the Catalog Backup Wizard	122
	About the Backup Policy Configuration Wizard	123
Chapter 8	Upgrading NetBackup software	125
	About upgrading NetBackup	125
	About the NetBackup 7.x Upgrade Portal	125
Chapter 9	Removing NetBackup server software	127
	About NetBackup server software removal on UNIX systems	127
	Removing NetBackup from UNIX servers	128
	About NetBackup server software removal on Windows systems	137
	Removing NetBackup server software on Windows systems	137
	Removing NetBackup server software in a clustered environment	140
	Removing NetBackup LiveUpdate from Windows systems	140
	About removal of the Java Console state data from Windows servers and Windows clients	141
Chapter 10	Removing NetBackup client software	142
	About NetBackup software removal on UNIX/Linux clients	142
	Removing NetBackup from UNIX/Linux clients	142

	Removing NetBackup Windows client software	149
Chapter 11	Reference	150
	About the NetBackup Java Runtime Environment	150
	Using NetApp disk arrays with Replication Director	150
	Security updates to the NetBackup database	154
Index		155

Preparing for installation

This chapter includes the following topics:

- [Restrictions on the NetBackup installation directory](#)
- [About compatibility between NetBackup versions](#)
- [About Symantec Operations Readiness Tools](#)
- [Recommended SORT procedures for new installations](#)
- [Recommended SORT procedures for upgrades](#)
- [About NetBackup software availability](#)
- [About storage device configuration](#)
- [How to install NetBackup](#)
- [About security certificates for NetBackup media servers](#)

Restrictions on the NetBackup installation directory

Each NetBackup supported file system defines restrictions on file and folder names for the installation folder. Please consult the file system vendor provided documentation for more details on the file and the folder name restrictions. Additionally, NetBackup supports only certain characters for the installation folder name. Use of non-supported characters can produce unexpected results and possibly result in lost data. The NetBackup supported characters for the installation folder are:

- UNIX/Linux
The POSIX fully portable file name characters (A-Z a-z 0-9 . _ -)
- Windows
The printable characters within the ASCII 7-bit range

Note: On Traditional Chinese and Korean versions of Windows, if the NetBackup client is installed to a path that contains a space, restore operations may fail. An example of a path with a space is `C:\Program Files`. Make sure to install the NetBackup client software to a path that does not contain a space on these versions of Windows.

About compatibility between NetBackup versions

You can run mixed versions of NetBackup between master servers, media servers, and clients. This back-level support lets you upgrade NetBackup one server at a time, which minimizes the effect on overall system performance. Symantec supports only certain combinations of servers and clients. The NetBackup catalog resides on the master server. Therefore, the master server is considered to be the client for a catalog backup. If your NetBackup configuration includes a media server, it must use the same NetBackup version as the master server to perform a catalog backup.

For complete information about compatibility between NetBackup versions, see the *NetBackup Release Notes* for version 7.7.1.

<http://www.symantec.com/docs/DOC8512>

Symantec recommends that you review the End of Support Life information available online.

<http://www.symantec.com/docs/TECH74757>

See “[About NetBackup software availability](#)” on page 18.

About Symantec Operations Readiness Tools

Symantec Operations Readiness Tools (SORT) is a robust set of standalone and web-based tools that support Symantec enterprise products. For NetBackup, SORT provides the ability to collect, analyze, and report on host configurations across UNIX/Linux or Windows environments. This data is invaluable when you want to assess if your systems are ready for an initial NetBackup installation or for an upgrade.

Access SORT from the following webpage:

<https://sort.symantec.com/netbackup>

Once you get to the SORT page, more information is available as follows:

- **Installation and Upgrade Checklist**

Use this tool to create a checklist to see if your system is ready for a NetBackup installation or an upgrade. This report contains all the software and the hardware compatibility information specific to the information provided. The report also includes product installation or upgrade instructions, as well as links to other references.

- **Hot fix and EEB Release Auditor**
 Use this tool to find out whether a release that you plan to install contains the hot fixes that you need.
- **Custom Reports**
 Use this tool to get recommendations for your system and Symantec enterprise products.
- **NetBackup Future Platform and Feature Plans**
 Use this tool to get information about what items Symantec intends to replace with newer and improved functionality. The tool also provides insight about what items Symantec intends to discontinue without replacement. Some of these items include certain NetBackup features, functionality, 3rd-party product integration, Symantec product integration, applications, databases, and the OS platforms.

Help for the SORT tools is available. Click **Help** in the upper right corner of the SORT home page. You have the option to:

- Page through the contents of the help similar to a book
- Look for topics in the index
- Search the help with the search option

Recommended SORT procedures for new installations

Symantec recommends new NetBackup users perform the three procedures that are listed for an initial introduction to SORT. The tool has many other features and functions, but these serve as a good introduction to SORT. In addition, the procedures provide a helpful base of knowledge for other SORT functionality.

Table 1-1

Procedure	Details
Create a SymAccount profile on the SORT webpage	See "To create a SymAccount profile on the SORT page" on page 13.
Create generic installation reports	See "To create a generic installation checklist" on page 13.

Table 1-1 (continued)

Procedure	Details
Create system-specific installation reports	See "To create a system-specific installation report for Windows" on page 14. See "To create a system-specific installation report for UNIX or Linux" on page 15.

To create a SymAccount profile on the SORT page

- 1 In your web browser, navigate to:
<https://sort.symantec.com/netbackup>
- 2 In the upper right corner, click **Register**.
- 3 Enter the requested login and contact information:

Email address	Enter and verify your email address
Password	Enter and verify your password
First name	Enter your first name
Last name	Enter your last name
Company name	Enter your company name
Country	Enter your country
Preferred language	Select your preferred language
CAPTCHA text	Enter the displayed CAPTCHA text. If necessary, refresh the image.
- 4 Click **Submit**.
- 5 When you receive your login information, you can log into SORT and begin uploading your customized information.

To create a generic installation checklist

- 1 In your web browser, navigate to:
<https://sort.symantec.com/netbackup>
- 2 Find the **Installation and Upgrade Checklist** widget.

3 Specify the requested information

Product	Select the appropriate product from the drop-down menu. For NetBackup select NetBackup Enterprise Server or NetBackup Server .
Product version you are installing or upgraded to	Select the correct version of NetBackup. The most current version is always shown at the top of the list.
Platform	Select the operating system that corresponds to the checklist you want generated.
Processor	Select the correct processor type for your checklist.
Product version you are upgrading from (optional)	For new installations, do not make any selections. For upgrades, you can select the currently installed version of NetBackup.

4 Click **Generate Checklist.**

- 5** A checklist corresponding to your choices is created. You can modify your selections from this screen, and click **Generate Checklist** to create a new checklist.

You can save the resulting information as a PDF. Numerous options are available for NetBackup and many of them are covered in the generated checklist. Please spend time reviewing each section to determine if it applies to your environment.

To create a system-specific installation report for Windows

- 1** Go to the SORT website:
<https://sort.symantec.com/>
- 2** Select **SORT > SORT for NetBackup**
- 3** In the **Custom Reports Using Data Collectors**, select the **Data Collector** tab.
- 4** Select the radio button for **Graphical user interface** and download the correct data collector for your platform.

The data collector is OS-specific. To collect information about Windows computers, you need the Windows data collector. To collect information about UNIX computers, you need the UNIX data collector.

- 5** Launch the data collector after it finishes downloading.

- 6 On the **Welcome** screen, select **NetBackup** from the product family section and click **Next**.
- 7 On the **System Selection** screen, add all computers you want analyzed. Click **Browse** to see a list of computers you can add to the analysis. Symantec recommends starting the tool with an administrator or a root account.
- 8 When all systems are selected, review the **System names** section and click **Next**.
- 9 In the **Validation Options** screen, under **Validation options**, select the version to which you plan to upgrade.
- 10 Click **Next** to continue
- 11 The utility performs the requested checks and displays the results. You can upload the report to My SORT, print the results, or save them. Symantec recommends that you upload the results to the My SORT website for ease of centralized analysis. Click **Upload** and enter your My SORT login information to upload the data to My SORT.
- 12 When you are finished, click **Finish** to close the utility.

To create a system-specific installation report for UNIX or Linux

- 1 Go to the SORT website:
<https://sort.symantec.com/>
- 2 Select **SORT > SORT for NetBackup**
- 3 Change to directory that contains downloaded utility.
- 4 In the **Custom Reports Using Data Collectors**, select the **Data Collector** tab.
- 5 Download the appropriate data collector for your platform.

The data collector is OS-specific. To collect information about Windows computers, you need the Windows data collector. To collect information about UNIX computers, you need the UNIX data collector.
- 6 Run `./sortdc`

The utility performs checks to confirm the latest version of the utility is installed. In addition, the utility checks to see it has the latest data. The utility then lists the location of the log file for this session.
- 7 If requested, press **Enter** to continue.
- 8 Select the **NetBackup Family** at the **Main Menu**.

9 Select Installation/Upgrade report when prompted What task do you want to accomplish?

You can select multiple options by separating your response with commas.

10 Specify the system or systems you want included in the report.

If you previously ran a report on the specified system, you may be prompted to run the report again. Select **Yes** to re-run the report.

The utility again lists the location of the log files for the session.

The progress of the utility is displayed to the screen.

11 Specify NetBackup when prompted for the product you want installation or upgrade reports.

12 Enter the number that corresponds to the version of NetBackup you want to install.

The utility again lists the location of the log files for the session.

The progress of the utility is displayed to the screen.

13 The utility prompts you to upload the report to the SORT website if you want to review the report online. The online report provides more detailed information than the text-based on-system report.

14 When your tasks are finished, you can exit the utility. You have the option to provide feedback on the tool, which Symantec uses to make improvements to the tool.

Recommended SORT procedures for upgrades

Symantec recommends current NetBackup users perform the three procedures that are listed for an initial introduction to SORT. The tool has many other features and functions, but these serve as a good introduction to SORT for users who already use NetBackup. In addition, the procedures provide a helpful base of knowledge for other SORT functionality.

Table 1-2

Procedure	Details
Create a SymAccount profile on the SORT webpage	See "To create a SymAccount profile on the SORT page" on page 13.

Table 1-2 (continued)

Procedure	Details
Create a system-specific upgrade report	See "To create a system-specific installation report for Windows" on page 14. See "To create a system-specific installation report for UNIX or Linux" on page 15.
Review the future platform and feature plans. Review the hot fix and emergency engineering binary release auditor information.	See "To review future platform changes and feature plans" on page 17. See "To review hot fix and emergency engineering binary information" on page 17.

To review future platform changes and feature plans

- 1 In your web browser, navigate to:
<https://sort.symantec.com/netbackup>
- 2 Find the **NetBackup Future Platform and Feature Plans** widget.
- 3 Click **Display Information**.
- 4 Review the information provided
- 5 Optional - sign in to create notification - Click **Sign in and create notification**.

To review hot fix and emergency engineering binary information

- 1 In your web browser, navigate to:
<https://sort.symantec.com/netbackup>
- 2 Find the **NetBackup Hot Fix and EEB Release Auditor** widget.
- 3 Enter the hot fix or emergency engineering binary (EEB) information.
- 4 Click **Search**.
- 5 The new page shows a table with the following columns:

Hot fix of EEB Identifier	Shows the hot fix or EEB number that was entered on the previous screen.
Description	Displays a description of the problem that is associated with the hot fix or EEB.
Resolved in Versions	Provides the version of NetBackup where this issue is resolved.

About NetBackup software availability

NetBackup 7.7.1 is available in the following formats:

- DVD media kit
 All necessary software and documentation files are provided on several DVDs. See [“About the NetBackup media kit”](#) on page 18.
- Electronic Software Distribution (ESD) images
 The DVD image files are posted and available for download on the **FileConnect** website. See [“About the NetBackup Electronic Software Distribution \(ESD\) images”](#) on page 19.

About the NetBackup media kit

The media kit includes a DVD for each supported UNIX platform or operating system and one DVD for Windows. The label on each DVD provides a brief description of its contents. Printed materials in the kit include a copy of the *NetBackup Getting Started Guide*.

[Table 1-3](#) describes the contents of each DVD.

Table 1-3 NetBackup 7.7.1 DVD contents

Platform OS	Contents
AIX 64-bit	Server and supported options
HP-UX IA64	Server and supported options
Linux RedHat x86_64	Server and supported options
Linux SUSE x86_64	Server and supported options
Solaris SPARC64	Server and supported options
Solaris x86-64	Server and supported options
Windows	<ul style="list-style-type: none"> ■ Server and supported options ■ All x64 clients ■ All x86 clients
Linux zSeries RedHat x64	Media server and supported options
Linux zSeries SUSE x64	Media server and supported options

Table 1-3 NetBackup 7.7.1 DVD contents (*continued*)

Platform OS	Contents
UNIX clients 1	<ul style="list-style-type: none"> ■ AIX ■ FreeBSD ■ HP PA-RISC and IA64 ■ Mac ■ Solaris SPARC and X86
UNIX clients 2	All Linux platforms
Clients in LiveUpdate format 1	<ul style="list-style-type: none"> ■ AIX ■ HP IA64 ■ All Linux platforms ■ Solaris SPARC and X86
Clients in LiveUpdate format 2	<ul style="list-style-type: none"> ■ HP PA-RISC ■ FreeBSD ■ Mac ■ All Windows platforms
OpsCenter for Windows	All Windows platforms
OpsCenter for UNIX/Linux	All UNIX/Linux platforms
OpenVMS (CD format)	NetBackup Client for OpenVMS

Note: The NetBackup vCenter plug-in for ESX is available electronically from the Symantec Fileconnect download site. It is free to customers under maintenance contract. An e-mail with access information to the Symantec Fileconnect download site was sent when NetBackup 7.6.1 became generally available. More information is available.

See [“About the NetBackup Electronic Software Distribution \(ESD\) images”](#) on page 19.

See [“About the NetBackup Electronic Software Distribution \(ESD\) images”](#) on page 19.

About the NetBackup Electronic Software Distribution (ESD) images

The ESD images for NetBackup 7.7.1 are available for download from the **FileConnect** webpage. The images adhere to a 1.8G size limitation.

To ensure the accuracy of the ESD download, some of the product images have been split into smaller, more manageable files. Before you uncompress any file, you must first join the split image files that you can identify as 1 of 2 and 2 of 2. A `Download Readme.txt` file on **FileConnect** describes how to join the files together.

See “About NetBackup software availability” on page 18.

See “About the NetBackup media kit” on page 18.

About storage device configuration

Reliable use of NetBackup depends on the proper configuration of your storage devices. To ensure reliable backups and restores, you must first install and configure devices to work with the operating system.

Before you install NetBackup, use the following guidelines to configure storage devices to work with the operating system:

New installations	Before you install NetBackup, Symantec recommends that you install and configure your devices with the latest version of drivers.
Connections and settings	<p>To prepare and connect new devices, perform the following tasks:</p> <ul style="list-style-type: none"> Set the SCSI ID (target). Make sure that it is set to an available SCSI ID. Physically attach your device to a compatible host bus adapter where that SCSI ID is available. <p>Compatible means that both the device and the host bus adapter are of the same type. For example, single-ended, high-voltage differential, low voltage differential, or Fibre Channel.</p>
Configuration	<p>To configure storage devices to work with the operating system, refer to the following documentation:</p> <ul style="list-style-type: none"> The instructions from the device and the operating system vendors. The <i>NetBackup Device Configuration Guide</i>. See the chapter that is appropriate for your operating system. http://www.symantec.com/docs/DOC5332
NetBackup installation	After all storage devices are installed, configured, and verified to work with the operating system, you can install NetBackup.

Warning: An improperly configured device can lead to backup failures, data loss, or both.

See “[About NetBackup server installation requirements for UNIX/Linux systems](#)” on page 32.

See “[Requirements for Windows NetBackup server installation](#)” on page 53.

Locating supported robot types

You can find a list of the supported robot types in the *Hardware Compatibility List (HCL)*.

For your convenience, Symantec periodically updates this document on the Symantec support website

To find the latest robot types that this release supports

- ◆ Click on the following link to access the *Hardware Compatibility List (HCL)*:
<http://www.netbackup.com/compatibility>

How to install NetBackup

For new NetBackup installations, install the software in the following order:

- | | |
|--------|--|
| Step 1 | Install master server software. |
| Step 2 | Install media server software (NetBackup Enterprise only). |
| Step 3 | Install the NetBackup Remote Administration Console (optional). |
| Step 4 | Install client software. |
| Step 5 | Install any NetBackup add-on products (such as language packages). |

Before you proceed with any installation procedure, be sure to review the installation requirements.

Note: NetBackup supports software system management standards. To support software system management standards, NetBackup installs two XML files on each NetBackup host. These files do not affect NetBackup functionality. In addition, you can identify these files by the suffix `.swidtag`.

See “[Requirements for Windows NetBackup server installation](#)” on page 53.

See [“About NetBackup server installation requirements for UNIX/Linux systems”](#) on page 32.

About the NetBackup preinstall checker

Starting with NetBackup 7.6, the server installer for both the UNIX/Linux and the Windows platforms includes a new preinstall checker. This feature helps to determine if your server is ready for a successful installation or upgrade.

Note: This feature is different than the NetBackup preinstallation Environment Checker that was released with the Windows version of NetBackup 7.1.

The check runs automatically when you start an installation on a master or a media server. The results of the check are shown at the following point:

- UNIX/Linux upgrade script
After you answer the question for participation in the NetBackup Product Improvement Program.
- Windows installation wizard
On the **Ready to Install the Program** screen, where the **Installation Summary** appears.

One of the tests that is performed is a comparison of the locally installed Emergency Engineering Binary (EEB) updates with the fixes included with the version of NetBackup being installed. If any of the preinstall tests fail, a message appears to indicate what type of action is required.

Some test failures are considered minor and let you continue with the installation or the upgrade. Critical test failures prevent the installation or the upgrade from happening. The output informs you that other action must be taken before you can proceed safely with the installation or the upgrade.

The preinstall check results are stored in the following locations:

- UNIX
In the installation trace file in the following path:
`/usr/openv/tmp`
- Windows
In the following directory:
`%ALLUSERSPROFILE%\Symantec\NetBackup\InstallSummary\`

See [“About Symantec Operations Readiness Tools”](#) on page 11.

About the NetBackup Product Improvement Program

Starting with NetBackup 7.5, the NetBackup Product Improvement Program captures installation deployment and product usage information.

During the NetBackup installation, you can choose to participate in the NetBackup Product Improvement Program and send this information automatically and securely to Symantec. The information that Symantec receives becomes part of a continuous quality improvement program that helps understand how customers configure, deploy, and use the NetBackup product. This information is then used to help Symantec identify improvements in product features, testing, technical support, and future requirements.

To learn more about the NetBackup Product Improvement Program, refer to the NetBackup license agreement section 17.18 Data Collection; Data Protection Regulations. The following describes where to find the license agreement:

- **UNIX**
 In the base directory of the UNIX images on the DVD media or from the downloaded media images from FileConnect, see the file `LICENSE`.
- **Windows**
 From the DVD media or the downloaded media images from FileConnect, start the installation wizard (`Browser.exe`). On the **Home** page, click **Installation**. On the **Installation** page, select either **Server Software Installation** or **Client Software Installation**. On the **Welcome** page, click **Next** to advance to the **License Agreement** page.

About security certificates for NetBackup media servers

NetBackup requires that media servers have a digital security certificate so that they function correctly in the following use cases:

- | | |
|---|---|
| NetBackup Administration Console authorization for Enhanced Auditing | In the Enhanced Auditing mode, a security certificate is mandatory when a user wants to connect to a media server through the NetBackup Administration Console .
See the <i>NetBackup Security and Encryption Guide</i> : |
| For cloud storage | The NetBackup CloudStore Service Container requires that a certificate be installed on the media server. If one is not installed, the Service Container cannot start.
See the <i>NetBackup Cloud Administrator's Guide</i> : |

For the procedure to generate security certificates for media servers, see the *NetBackup Administrator's Guide, Volume I* or the *NetBackup Cloud Administrator's Guide*:

<http://www.symantec.com/docs/DOC5332>

NetBackup licenses

This chapter includes the following topics:

- [About NetBackup license key requirements](#)
- [About NetBackup license compatibility](#)
- [About license key entry](#)
- [Frequently asked questions about license keys](#)

About NetBackup license key requirements

To install NetBackup master server or media server software, you must enter a NetBackup product license key.

To obtain license keys, you must order a license SKU when you order your NetBackup products.

After you place your order, Symantec sends you an email with a license certificate that includes the following information:

List of NetBackup licenses purchased

This list includes all of the licenses for the products that you ordered.

Keep this list in a secure location. You may be asked for a product license key if you ever need to contact technical support for assistance.

Serial number for access to download NetBackup products

Instead of a DVD media kit, you can use this serial number to download the Electronic Software Distribution (ESD) images for NetBackup product installation.

Go to the following website and enter this serial number to download the ESD images to your system:

<https://fileconnect.symantec.com/LangSelection.jsp>

When you install NetBackup, Symantec recommends that you enter all other product license keys on the master server when you are prompted. Although you can add these license keys later, it is easier to enter them when you install the master server software.

For detailed information on how to administer NetBackup license keys, refer to the *NetBackup Administrator's Guide, Volume I*.

<http://www.symantec.com/docs/DOC5332>

About NetBackup license compatibility

To use your current NetBackup license keys to upgrade servers, add-on products, and database agents to NetBackup 7.7.1, the following are required:

- NetBackup versions 6.x or 7.0.x must already be installed.
- You must have a valid maintenance contract for all licensed NetBackup products.

Note: You cannot upgrade to NetBackup 7.7.1 if your current installed version is NetBackup 5.x. You must first upgrade to NetBackup 6.0 or 6.5, and then you can upgrade to NetBackup 7.5. Any 6.x version can be upgraded directly to 7.7.1.

Upgrade licenses and software may be obtained from the Symantec Licensing Portal at the following website:

<https://licensing.symantec.com/acctmgmt/index.jsp>

For detailed information and procedures on how to administer license keys, refer to the *NetBackup Administrator's Guide, Volume I*.

<http://www.symantec.com/docs/DOC5332>

See “About license key entry” on page 26.

About license key entry

License keys for all NetBackup SKUs must be entered on the master server. License keys for some SKUs must also be entered on the media server, depending on the capabilities that you require for the media server.

[Table 2-1](#) describes the license keys that must be entered on each server.

Table 2-1 Required license keys for NetBackup media servers

Media server type	Required licenses (based on media server capabilities)
Enterprise media servers	<ul style="list-style-type: none"> ■ NetBackup Enterprise Server 7.7.1 UNIX ■ NetBackup Enterprise Server 7.7.1 WIN/LNX/SOLX64 ■ NetBackup Standard Infrastructure 7.7.1 XPLAT1 Front End TBYTE ■ NetBackup Enterprise Infrastructure 7.7.1 XPLAT1 Front End TBYTE ■ NetBackup Platform Base ■ NetBackup Option Library Based Tape Drive 7.7.1 XPLAT ■ NetBackup Option Shared Storage Option 7.7.1 XPLAT ■ NetBackup Option NDMP 7.7.1 XPLAT ■ NetBackup Media Server Encryption Option for Enterprise Server, UNIX ■ NetBackup Media Server Encryption Option for Enterprise Server, Windows/Linux
SAN media servers	<ul style="list-style-type: none"> ■ NetBackup Enterprise Client, UNIX ■ NetBackup Enterprise Client, Windows/Linux ■ Media Server Encryption Option for SAN Media Server (Enterprise Client), UNIX ■ Media Server Encryption Option for SAN Media Server (Enterprise Client), Windows/Linux

Enter license keys by using one of the following methods:

- During NetBackup master server and media server installation (recommended)
 The installation script prompts you to enter the license keys for all NetBackup products that you plan to install.
- NetBackup Administration Console
 After NetBackup master server or media server installation, open the console and click **Help > License Keys**.
- Command-line interface (UNIX only)
 After NetBackup master server or media server installation, use the following command:

```
/usr/opensv/netbackup/bin/admincmd/get_license_key
```

Note: You can log on to a NetBackup server from almost any server in a system to view, enter, and administer license keys. When you administer license keys remotely, make sure that you view the licenses of the system you intend to change. You do not want to add or change a license key on the wrong server.

Frequently asked questions about license keys

Symantec customers have asked the following questions about how to manage license keys.

Is the license system for NetBackup the same as the license system in other Symantec products?

NetBackup uses a common license system that other Symantec products also use. Please remember, however, that the common license system provides flexibility in the license features that each product implements. For example, NetBackup does not have a node-locked license system, but some other products do.

Can I use NetBackup if all I have is a media kit?

No. The media kit by itself does not allow any access to NetBackup. You always need a license key (either permanent or evaluation). License keys should always be delivered with the media kit, so you should never find yourself with a media kit and no key.

What does the license key look like? What information does it contain?

The key is a multi-digit alphanumeric string (for example: 8EPP-ABCD-9XYZ-XYZ9-8881-VCF4-OIUF-AJDC). The key contains information on the following:

- Whether the key is for NetBackup Server or NetBackup Enterprise Server
- Whether the key is for a server, a client, an agent, or an option (and which one)
- Whether the key is a permanent key or an evaluation key
- Information about how and where the key was generated

Is the license key serialized?

Yes, serialization information is embedded in the key.

Can I see reports on what license keys I have?

Yes. Information about license keys is stored on the master server.

To access the information, open the NetBackup Administration Console and select **Help > License Keys**.

On UNIX servers, you can also run the following command:

```
/usr/opensv/netbackup/bin/admincmd/get_license_key
```

For more information on how to view reports, refer to the *NetBackup Administrator's Guide, Volume I*.

<http://www.symantec.com/docs/DOC5332>

How do I enable options and agents?

When you install NetBackup, you are prompted to enter the license keys for all options and agents.

If you purchase an agent or other add-on product at a later date, you can enter its license key manually. Open the NetBackup Administration Console and select **Help > License Keys**.

On UNIX servers, you can also run the following command:

```
/usr/opensv/netbackup/bin/admincmd/get_license_key
```

Some options require that you have your original NetBackup DVDs, because additional binaries must be installed. You should always keep your NetBackup DVDs in a safe place.

Should I save license keys after they have been entered?

Yes. Always store copies of your license keys in a secure place.

What should I do if I have lost my license key(s)?

Symantec has a record of all license keys that are issued to customers. Customers who lose their license key(s) can call Order Management to get copies of their license keys.

- For Americas, Japan, PacRim, Australia:
650.318.4265 FAX: 650.335.8428
- For Europe, Middle East and Africa:
00.353.61.365232 FAX: 00.353.61.365223

If you have purchased NetBackup from a Symantec partner, you need to contact that partner for information on your key.

<p>How are large volume orders handled?</p>	<p>Many NetBackup installations are very large, and the license keys are long. License keys that you enter multiple times can be time-consuming. You can request a single license key for each type of NetBackup component you purchase. For example, you can obtain one license key for use with 50 Oracle agents. Site licenses enable unrestricted use for specific NetBackup agents or options.</p> <p>You still need a unique license key for each type of NetBackup component that you purchase. Separate license keys are required for components like NetBackup Server, a Lotus Notes agent, or any NDMP option.</p>
<p>What about license keys for customers with site licenses?</p>	<p>Site licenses are handled much like large volume orders are. The certificate for a site license states that the license key is good for unlimited copies.</p>
<p>Do I need a license key to enable NetBackup Remote Administration Consoles?</p>	<p>No. NetBackup Remote Administration Consoles do not require special license keys. You can install them on any computer with access to the master server.</p>
<p>Can a license key be used multiple times?</p>	<p>Yes. You can use your license keys multiple times. You are, however, legally bound to install and use only the number of NetBackup servers, clients, agents, and options for which you purchase licenses.</p>
<p>How do existing customers get license keys?</p>	<p>All NetBackup customers who have current maintenance contracts with Symantec automatically receive the latest version of NetBackup. You receive the NetBackup media kit and license keys for every component for which you purchased licenses.</p> <p>If your maintenance is through a Symantec partner, you upgrade through the partner. Contact the partner for more details.</p>
<p>What if I do not get the right license keys?</p>	<p>If you believe that you received an incorrect license key, contact Order Management using the number on your license key certificate. Technical support does not issue permanent license keys. You can obtain license keys only through Order Management. Technical support can provide temporary one-month license keys to you while issues regarding permanent license keys are resolved.</p>
<p>What does an evaluation license key enable?</p>	<p>The evaluation license key enables unrestricted use of NetBackup, its agents, and its options for a predetermined period of time.</p>

Am I notified when an evaluation is about to expire?

To find out when a license key expires, open the NetBackup Administration Console and select **Help > License Keys**.

On UNIX servers, you can also run the following command:

```
/usr/opensv/netbackup/bin/admincmd/get_license_key
```

What happens when an evaluation license key expires?

The NetBackup services or daemons are shut down. When you attempt to use the product you are informed that its evaluation period has expired.

Does NetBackup save the backup configuration and catalog information when evaluation license keys expire?

Yes. Customers who add a permanent license key to an evaluation version of NetBackup have immediate access to their catalog information and configuration information.

How do I upgrade from an evaluation license to a permanent license?

It is easy. When you purchase a permanent license, you add that license to NetBackup. All the configuration information and catalog data from your evaluation version is retained.

To enter your permanent license key, open the NetBackup Administration Console and select **Help > License Keys**.

On UNIX servers, you can also run the following command:

```
/usr/opensv/netbackup/bin/admincmd/get_license_key
```

Installing server software on UNIX systems

This chapter includes the following topics:

- [About NetBackup server installation requirements for UNIX/Linux systems](#)
- [How the installation script works](#)
- [About mounting the NetBackup software media](#)
- [Installing NetBackup master server software on UNIX](#)
- [Installing NetBackup media server software on UNIX](#)
- [About pushing client software from a master server to clients](#)
- [Installing NetBackup add-on products](#)
- [How to configure the window manager for the Java Interface \(NetBackup-Java compatible platforms\)](#)

About NetBackup server installation requirements for UNIX/Linux systems

Before you install NetBackup, make sure that your backup environment meets the following requirements:

Table 3-1

Item	Description
General requirements	<p>Make sure that you have the following hardware and software already set-up:</p> <ul style="list-style-type: none"> ■ All NetBackup installation DVDs or ESD images, appropriate license keys, and the root password for all servers. ■ The <code>gzip</code> and the <code>gunzip</code> commands must be installed on the local system. The directories where these commands are installed must be part of the root user's <code>PATH</code> environment variable setting. ■ A server of a supported hardware type that runs a supported version of its operating system (with applicable patches), adequate disk space, and supported peripherals. For details on these requirements, refer to the <i>NetBackup Release Notes</i>. ■ All NetBackup servers must recognize and be recognizable by their client systems. In some environments, this means that each must be defined in the other's <code>/etc/hosts</code> file. Other environments may use the Network Information Service (NIS) or Domain Name Service (DNS). ■ For reasonable performance of the NetBackup-Java interfaces, you need 512 MB of RAM. Of that space, 256 MB must be available to the interface program (<code>jnbSA</code> or <code>jbpSA</code>). ■ The minimum screen resolution configuration is 1024x768, 256 colors.
Other backup software	<p>Symantec recommends that you remove any other vendor backup software currently configured on your system before you install this product. Other vendor backup software can negatively affect how NetBackup installs and functions.</p>
Media servers	<p>Ignore references to media servers if you do not plan to install any separate media servers.</p>
Memory considerations	<ul style="list-style-type: none"> ■ Master servers in a production environment with several database agents enabled, should have a minimum of 8 GB of memory each. ■ Media servers in a production environment should have a minimum of 4 GB of memory each. ■ Any client in a production environment should have a minimum of 512 MB of memory. ■ For reasonable performance of the NetBackup-Java interfaces, you need 512 MB of RAM. Of that space, 256 MB must be available to the interface program (<code>jnbSA</code> or <code>jbpSA</code>). ■ For additional information about memory requirements, refer to the <i>NetBackup Backup Planning and Performance Tuning Guide</i>. http://www.symantec.com/docs/DOC5332

Table 3-1 (continued)

Item	Description
Disk space considerations	<p>On the NetBackup server, the installation directory contains the software and the NetBackup catalog. Both of these can become quite large.</p> <p>If space is an issue, you can install NetBackup on an alternate file system. The installation lets you select an alternate install location, and creates the appropriate link from <code>/usr/opensv</code>.</p> <p>For additional information about disk space requirements, refer to the <i>NetBackup Getting Started Guide</i>.</p> <p>http://www.symantec.com/docs/DOC5332</p>
NFS compatibility	<p>Symantec does not support installation of NetBackup in an NFS-mounted directory. File locking in NFS-mounted file systems can be unreliable.</p>
Kernel reconfiguration	<p>For some peripherals and platforms, kernel reconfiguration is required.</p> <p>For more details, see the <i>NetBackup Device Configuration Guide</i>.</p> <p>http://www.symantec.com/docs/DOC5332</p>
Red Hat Linux	<p>For Red Hat Linux, NetBackup requires server networking.</p>

Do not mix non-English versions of Windows and UNIX platforms unless master and media servers are NetBackup appliances

Do not mix non-English versions of Windows and UNIX platforms unless your master servers and media servers are NetBackup appliances. If you mix non-English versions of Windows and UNIX platforms, differences in operating system architecture and encodings may cause non-ASCII file names and folder names to display incorrectly within the user interface. This issue may cause functional failures.

NetBackup installations on environments that run different versions of UNIX-based operating systems

NetBackup can be installed in environments that run different versions of UNIX-based operating systems as long as the system locales are identical. The use of different locales across UNIX platforms may cause non-ASCII file names and folder names to display incorrectly within the user interface. This issue may cause functional failures.

Special installation guidelines for Solaris systems

Several kernel-tunable parameters, such as Message Queue, Semaphore, and Shared Memory Parameters, can affect NetBackup performance. If you adjust these values, you may prevent your system performance from slowing down or even reaching a deadlock state.

More information about tunable parameters is available online.

- Recommended NetBackup *NIX semaphore tuning values (Linux/Solaris/HP-UX/AIX)
<http://www.symantec.com/docs/TECH203066>
- Tuning Solaris 10 for NetBackup
<http://www.symantec.com/docs/TECH63229>
- Tuning Solaris 10 shared memory for NetBackup Media Server processes (bptm / bpdm)
<http://www.symantec.com/docs/TECH62633>
While this link refers to NetBackup 6.x, the information remains valid for NetBackup 7.x.

For more information about parameter definitions and examples, see the *NetBackup Backup Planning and Performance Tuning Guide* on the support website.

<http://www.symantec.com/docs/DOC5332>

Special installation guidelines for HP-UX systems

Use the following guidelines when you install NetBackup on HP-UX systems:

- Install NetBackup on a file system that supports long file names.
- During NetBackup installation, the following error may occur when the NetBackup database is created:

```
SQL error (-832) -- Connection error: Insufficient system
resources - failed to allocate a SYSV semaphore
```

To correct the error, increase the number of semaphores in the HP-UX kernel. For details on how to change HP-UX parameters, see the *NetBackup Backup Planning and Performance Tuning Guide, Chapter 11: OS-Related Tuning Factors*.

<http://www.symantec.com/docs/DOC5332>

Special installation guidelines for UNIX clustered environments

Use the following guidelines when you install NetBackup in clustered systems:

- Ensure that each node in the NetBackup cluster can run the `rsh` command or its equivalent (on HP-UX, the command is `remsh`). Starting with NetBackup 7.5, you can also use the `ssh` command. The root user must be able to perform a remote login to each node in the cluster without entering a password. This remote login is necessary for installation and configuration of the NetBackup server and any NetBackup options. After installation and configuration are completed, it is no longer required.
- You must install, configure, and start the cluster framework before you install NetBackup. For additional installation prerequisites and installation notes, see the *NetBackup Clustered Master Server Administrator's Guide*.
<http://www.symantec.com/docs/DOC5332>
- You must have defined a virtual name using DNS, NIS, or `/etc/hosts`. The IP address is defined at the same time. (The virtual name is a label for the IP address.) Use this virtual name and IP address only for the NetBackup resource.

How the installation script works

When you install NetBackup server software, client software is also installed.

When you install NetBackup 7.7.1, the following options are also installed if the platform supports them:

- BMR Master Server
- NDMP
- Symantec Product Authentication and Authorization (NetBackup Access Control)
- Vault
- BMR Boot Server
- DB2
- Encryption
- Informix
- LiveUpdate agent
- Lotus Notes
- Oracle
- SAP
- Snapshot Client
- Sybase

After installation is complete, a valid license key for each option must be entered to enable its functionality. Each option must also be configured as needed.

In addition to server software and options, the installation script performs the following tasks:

Host names	<p>Places the host name in the <code>/usr/opensv/netbackup/bp.conf</code> file on the server.</p> <p>For clustered environments, the script places the virtual host name in the <code>/usr/opensv/netbackup/bp.conf</code> file on the server.</p>
Automatic startup and shutdown scripts	<p>Adds automatic the startup and the shutdown scripts to the appropriate directories on the various supported platforms.</p>
PBX	<p>For the platforms that support PBX, NetBackup versions 7.x install or update PBX when the client software is installed.</p> <p>If the computer where you install NetBackup does not already have PBX and the platform supports it, the installation script installs PBX.</p> <p>If PBX already exists on the computer, the installation script performs one of the following tasks:</p> <ul style="list-style-type: none">■ Updates the existing version if it is older than the version that is included with 7.7.1.■ Does not update PBX if the existing version is the same or later than the version that is included with 7.7.1. <p>Note: If you upgrade from NetBackup 6.0 or 6.5, PBX may not upgrade correctly. If the PBX upgrade is not successful, use the ICS disk from your 6.0 or 6.5 package to remove the older version. For complete details, see the <i>Infrastructure Core Services Installation Guide</i> for those NetBackup versions.</p>

About mounting the NetBackup software media

Use the examples in the following table as guidelines when you mount NetBackup DVDs. Check with your hardware vendor to see if you may need to use other flags or options.

Table 3-2 Flags and options for mounting NetBackup DVDs

Flags or options	Defined
<code>-v, -t, -F</code>	Specifies the type of file system to mount.
<code>-o</code>	Translates the file names properly if required.
<code>-r</code>	Specifies that you want to mount the DVD for reading.
<code>device_path</code>	Specifies the name of the DVD drive.
<code>mount_point</code>	Specifies the directory where you want to mount the DVD.

See [“Mounting NetBackup software media on UNIX or Linux systems”](#) on page 38.

Mounting NetBackup software media on UNIX or Linux systems

The following procedure describes how to mount the NetBackup DVD on UNIX or Linux systems.

To mount the NetBackup DVD on UNIX or Linux systems

- 1 Log in as `root`.
- 2 Create a mount point (all except Solaris).

```
mkdir /dvd
```

3 (Conditional) on HP-UX systems earlier than 11.23, start PFS daemons.

```
nohup pfs_mountd &
nohup pfsd &
```

4 Issue the appropriate mount command for your operating system.

AIX `mount -v cdrfs -r device_path mount_point`

AIX `smitty cdrfs`

or

`smitty mountfs`

FreeBSD `mount -r -t cd9660 device_path mount_point`

HP-UX earlier than 11.23 `pfs_mount -o xlat=unix device_path mount_point`

To find the device path, you can run `ioscan -fn`.

HP-UX later than 11.23 `mount -F cdrfs device_path mount_point`

Linux `mount device_path mount_point`

Solaris If Volume Manager (`vold`) is running, the DVD mounts automatically.

If `vold` is not running, start it as follows:

```
/usr/sbin/vold &
```

Installing NetBackup master server software on UNIX

The master server manages backups, archives, and restores. The master server is where the NetBackup catalog resides which includes the internal databases that contain information about NetBackup configuration and backups.

Use the following guidelines for a new master server installation:

Designate master server

Designate the computer that you want to be the master server and install the master server software on that computer first.

EMM server	<p>Starting with NetBackup 7.6 you must configure EMM on the master server. All master servers must have their own EMM configuration. Remote EMM or shared EMM is no longer supported.</p>
License keys	<p>During master server installation, you must enter a NetBackup product license key. You must also enter license keys for any additional NetBackup product options or agents that are used on the server or its clients. These additional license keys must be entered on the master server.</p> <p>If you add, delete, or make and save any license key updates in the NetBackup-Java Administration Console, you must restart the console.</p> <p>For more information on how to administer NetBackup licenses, see the <i>NetBackup Administrator's Guide, Volume I</i>.</p> <p>http://www.symantec.com/docs/DOC5332</p>

To install NetBackup master server software

- 1 Log in to the server as root.
- 2 Use one of the following methods to start the installation script:

DVD	<ul style="list-style-type: none"> ■ Insert the NetBackup Server DVD for the appropriate platform into the drive. Check the DVD label to identify its contents. See “About the NetBackup media kit” on page 18. ■ If necessary, mount the DVD. See “About mounting the NetBackup software media” on page 37. ■ Enter the following command: <code>dvd_directory/install</code> The <code>dvd_directory</code> is the path to the directory where you can access the DVD.
ESD images (downloaded files)	<ul style="list-style-type: none"> ■ Navigate to the location where the installation images reside. ■ Enter the following command: <code>./install</code>

3 When the following message appears press **Enter** to continue:

```
Symantec Installation Script  
Copyright 1993 - 2013 Symantec Corporation, All Rights Reserved.
```

```
Installing NetBackup Server Software
```

```
Please review the SYMANTEC SOFTWARE LICENSE AGREEMENT located on  
the installation media before proceeding. The agreement includes  
details on the NetBackup Product Improvement Program.
```

```
For NetBackup installation and upgrade information specific to your  
platform and to find out if your installed EEBs or hot fixes are  
contained in this release, check out the Symantec Operations Readiness  
Tools (SORT) Installation and Upgrade Checklist and Hot fix and EEB  
Release Auditor, respectively, at https://sort.symantec.com/netbackup.
```

```
ATTENTION! To help ensure a successful upgrade to NetBackup 7.7.1,  
please visit the NetBackup 7.x Upgrade Portal:  
http://www.symantec.com/docs/TECH74584.
```

```
Do you wish to continue? [y,n] (y)
```

4 For the NetBackup installation location and the option to upload the installation and the platform information to Symantec, enter the appropriate platform information as follows:

- When the following question appears, press **Enter** to accept the default (**y**) or type **n** and press **Enter**:

```
Participate in the NetBackup Product Improvement  
Program? (y/n) [y]
```

- When the following question appears, press **Enter** to accept the default (**y**).

```
The NetBackup and Media Manager software is built  
for use on <platform> hardware. Do you want to install  
NetBackup and Media Manager files? [y,n] (y)
```

- When the following question appears, select where to install NetBackup and Media Manager software:

```
NetBackup and Media Manager are normally
installed in /usr/opensv.
Is it OK to install in /usr/opensv? [y,n] (y)
```

The path displayed for Solaris is /opt/opensv.

To accept the default (**y**), press **Enter**.

To change the installation location, type **n** and press **Enter**. Then enter the appropriate destination.

Additional information about installation folder restrictions is available.

See [“Restrictions on the NetBackup installation directory”](#) on page 10.

- 5 Enter the NetBackup Server or Enterprise Server license key.
- 6 Type **y**, then follow the prompts to add license keys for other NetBackup options and agents.

Although you can add license keys later, you should enter them now. If you add any license keys later through the NetBackup-Java Administration Console, you must restart the console.

- 7 After all license keys are entered, type **q** to quit the License Key Utility and complete the server software installation.
- 8 Verify or enter the correct computer name when prompted by the following message:

```
Installing NetBackup Enterprise Server version: 7.7.1
If this machine will be using a different network interface than
the default (name), the name of the preferred interface
should be used as the configured server name. If this machine
will be part of a cluster, the virtual name should be used as the
configured server name.
The domainname of your server appears to be "domain". You
may choose to use this domainname in your configured NetBackup
server name, or simply use "name" as the configured
NetBackup server name.
Would you like to use "name.domain" as the configured NetBackup server
name of this machine? [y, n] (y)
```

Note: Incorrect information for the domain name results in failures during the configuration of Authentication Broker and NetBackup Access Controls. To correct this problem, use the `bpbaz -configureauth` command to configure Authentication Broker. More information about the `bpbaz -configureauth` command is available.

Symantec NetBackup Commands Reference Guide

<http://www.symantec.com/docs/DOC5332>

- To accept the displayed (default) name, press **Enter**.
- To change the displayed (default) name, type **n** and enter the name that you want.
- For a clustered NetBackup server, enter the virtual name for the NetBackup server and not the actual local host name.

9 Identify or verify the master server by answering the following question when it appears:

```
Is <name> the master server? [y, n] (y)
```

- To accept the displayed name (which is the name that you identified in the previous step), press **Enter**.
- If you entered a virtual name for the server in the previous step, the installation script presents the following question:

```
Is this server part of a cluster installation?
```

If the answer is yes, press **y** and answer the series of cluster configuration questions that appear.

If the answer is no, press **n**.

10 Identify whether there are any media servers for this master server by answering the following question when it appears:

```
Do you want to add any media servers now? [y, n] (n)
```

- If there are no media servers for this master server, press **Enter** and proceed to the next step.
- If there are media servers for this master server, type **y** and enter the name of each media server.

When you enter the media server names, you must enter the computer name and the domain name. For example:

```
alpha.min.symantec.com
```

Where `alpha` is the computer name and `min.symantec.com` is the domain name.

The media server names that you enter here are added to the `bp.conf` file on the master server, automatically. After you install the media server software later, the master server can then communicate with the media servers immediately.

- To add a media server to an existing and an operational NetBackup environment, you cannot use the procedures in this guide. For complete details on how to add a media server to an existing and an operational NetBackup environment, see the *NetBackup Administrator's Guide, Volume II*.

<http://www.symantec.com/docs/DOC5332>

- 11 When the following message appears, press **Enter** and accept the default name of the EMM server. Starting with NetBackup 7.6 you must configure EMM on the master server. All master servers must have their own EMM configuration. Remote EMM or shared EMM is no longer supported.

```
NetBackup maintains a centralized catalog (separate from the
image catalog) for data related to media and device
configuration, device management, storage units, hosts and host
aliases, media server status, NDMP credentials, and other
information. This is managed by the Enterprise Media Manager
server.
```

```
Enter the name of the Enterprise Media Manager (default: <name>)
```

- 12 Answer the following question when it appears:

```
Do you want to start the NetBackup job-related processes so backups and
restores can be initiated? [y, n] (y)
```

- If you have (or want to have) a clustered NetBackup server, type **n**.
- For non-clustered installations, press **Enter** to accept the default answer (**y**) and start the NetBackup processes and the EMM server. You must start these processes now because the EMM server must be running when you install any media servers later.

- 13 For a clustered NetBackup master server, repeat these steps on every node on which you want to run NetBackup.

Continuing with NetBackup software installation

After you have installed the master server software, you are ready to install media server software or client software depending on your environment.

- If you have media servers in your system, you are ready to install media server software.
See [“Installing NetBackup media server software on UNIX”](#) on page 45.
- If there are no media servers in your environment, you are ready to install client software on client computers.
 - See [“Installing UNIX clients locally”](#) on page 100.
 - To install client software on clients from the master server location (recommended), you must first install the client type software on the master server.
See [“Installing client type software on a master server”](#) on page 50.

Installing NetBackup media server software on UNIX

This section describes how to install a new NetBackup media server. Use this information to install the server software on a computer with no existing version of NetBackup.

Media server software manages the robotic and the storage devices within your NetBackup environment.

After you have installed the master server and the EMM server software, you are ready to install media server software on media server computers.

Use the following guidelines when you install new media servers:

Designate media servers	Designate the computers that you want to be media servers and install the media server software on them.
Clusters	New or initial NetBackup 7.x media servers cannot be installed as clusters. However, existing media servers with NetBackup 6.x that are clustered can be upgraded to NetBackup 7.x and still remain clustered.
EMM server	The EMM server must be installed and running before you install media server software.

License keys When you install NetBackup media server software, you must enter a NetBackup product license key. You must also enter license keys for any additional NetBackup product options or agents that are used on the server or its clients. These additional license keys must be entered on each media server.

For more information on how to administer NetBackup licenses, see the *NetBackup Administrator's Guide, Volume I*.

<http://www.symantec.com/docs/DOC5332>

Note: If you make and save any license key changes in the NetBackup-Java Administration Console, you must restart the console.

IBMzSeries RedHat Starting with NetBackup 7.0.1, these platforms are supported for
and IBMzSeries SUSE use as media servers only.

To install NetBackup media server software

- 1 Log in to the server as root.
- 2 Use one of the following methods to start the installation script:

DVD

- Insert the NetBackup Server DVD for the appropriate platform into the drive.
Check the DVD label to identify its contents.
See “[About the NetBackup media kit](#)” on page 18.
- If necessary, mount the DVD.
See “[About mounting the NetBackup software media](#)” on page 37.
- Enter the following command:
`dvd_directory/install`
The *dvd_directory* is the path to the directory where you can access the DVD.

ESD images (downloaded files)

- Navigate to the location where the installation images reside.
- Enter the following command:
`./install`

3 When the following message appears, press **Enter** to continue:

```
Symantec Installation Script  
Copyright 1993 - 2013 Symantec Corporation, All Rights Reserved.
```

```
Installing NetBackup Server Software
```

```
Please review the SYMANTEC SOFTWARE LICENSE AGREEMENT located on  
the installation media before proceeding. The agreement includes  
details on the NetBackup Product Improvement Program.
```

```
For NetBackup installation and upgrade information specific to your  
platform and to find out if your installed EEBs or hot fixes are  
contained in this release, check out the Symantec Operations Readiness  
Tools (SORT) Installation and Upgrade Checklist and Hot fix and EEB  
Release Auditor, respectively, at https://sort.symantec.com/netbackup.
```

```
ATTENTION! To help ensure a successful upgrade to NetBackup 7.7.1,  
please visit the NetBackup 7.x Upgrade Portal:  
http://www.symantec.com/docs/TECH74584.
```

```
Do you wish to continue? [y,n] (y)
```

4 For the NetBackup installation location and the option to upload the installation and the platform information to Symantec, enter the appropriate platform information as follows:

- When the following question appears, press **Enter** to accept the default **(y)** or type **n** and press **Enter**:

```
Participate in the NetBackup Product Improvement  
Program? (y/n) [y]
```

- When the following question appears, press **Enter** to accept the default **(y)**.

```
The NetBackup and Media Manager software is built  
for use on <platform> hardware. Do you want to install  
NetBackup and Media Manager files? [y,n] (y)
```

- When the following question appears, select where to install NetBackup and Media Manager software:

```
NetBackup and Media Manager are normally
installed in /usr/opensv.
Is it OK to install in /usr/opensv? [y,n] (y)
```

The path displayed for Solaris is /opt/opensv.

To accept the default (**y**), press **Enter**.

To change the installation location, type **n** and press **Enter**. Then enter the appropriate destination.

Additional information about installation folder restrictions is available.

See [“Restrictions on the NetBackup installation directory”](#) on page 10.

- 5 Enter the NetBackup Server or NetBackup Enterprise Server license key.
- 6 Type **y**, then follow the prompts to add license keys for other NetBackup options and agents.

Although you can add license keys later, you should enter them now. If you add any license keys later through the NetBackup-Java Administration Console, you must restart the console.

- 7 After all license keys are entered, type **q** to quit the License Key Utility and complete the server software installation.
- 8 Verify or enter the correct computer name when prompted by the following message:

```
Installing NetBackup Enterprise Server version: 7.7.1
If this machine will be using a different network interface than
the default (name), the name of the preferred interface
should be used as the configured server name. If this machine
will be part of a cluster, the virtual name should be used as the
configured server name.
The domainname of your server appears to be "domain". You
may choose to use this domainname in your configured NetBackup
server name, or simply use "name" as the configured
NetBackup server name.
Would you like to use "name" as the configured NetBackup server
name of this machine? [y, n] (y)
```

Note: Incorrect information for the domain name results in failures during the configuration of Authentication Broker and NetBackup Access Controls. To correct this problem, use the `bpbaz -configureauth` command to configure Authentication Broker. More information about the `bpbaz -configureauth` command is available.

Symantec NetBackup Commands Reference Guide

<http://www.symantec.com/docs/DOC5332>

- If the displayed (default) media server name is correct, press **Enter**.
 - If the displayed (default) media server name is not correct, type **n** and enter the correct name.
- 9 Identify the master server that you have already installed, by answering the following question when it appears:

```
Is <name> the master server? [y,n]
```

- Type **n** and enter the fully qualified domain name of the master server.
 - If the master server is clustered, enter the virtual name of the master server.
- 10 When the following message appears, press **Enter** and accept the default name of the EMM server. Starting with NetBackup 7.6 you must configure EMM on the master server. All master servers must have their own EMM configuration. Remote EMM or shared EMM is no longer supported.

```
Enter the name of the Enterprise Media Manager (default: <name>)
```

The master server name is displayed by default.

- 11 Repeat steps 1 through 10 to install media server software on any remaining media servers.

About pushing client software from a master server to clients

You can increase the speed of client installation by pushing the software from the master server to the clients. This method eliminates the need for a local installation at each client.

The following describes how to prepare your NetBackup environment for client software installation from the master server.

- Install the client type software on the master server. Be sure to install all of the client types that pertain to your NetBackup configuration.
See “[Installing client type software on a master server](#)” on page 50.
- Before you can push client software from the master server, each client name must be assigned to a NetBackup policy. Policies are created on the master server.
When you create a policy, you must identify the policy type, which indicates the operating system on the clients that are assigned to that policy. Without a policy, the remote installation (or push) fails because the master server does not know the operating system of the client.
For information on how to create NetBackup policies, refer to the *NetBackup Administrator's Guide, Volume I*.
<http://www.symantec.com/docs/DOC5332>
- After the required policies are created, you can push client software from the master server to the clients.
See “[About remote installation methods for UNIX/Linux clients](#)” on page 102.

Installing client type software on a master server

Client type software must be installed on the master server to perform the following operations:

- Assign clients to NetBackup policies so that those clients can be backed up.
- Install (or push) client software from the master server to clients.
For each UNIX client type, the client installation script lets you install the client software onto the master server. You can then install (or push) the client software from the master server to the clients.

To install client type software on a master server

- 1 Log in to the server as root.
- 2 Use one of the following methods to start the installation script:

DVD

- Insert the NetBackup UNIX Clients DVD into the drive.
See “[About the NetBackup media kit](#)” on page 18.
- If necessary, mount the DVD.
See “[About mounting the NetBackup software media](#)” on page 37.
- Enter the following command:

```
dvd_directory/install
```


The *dvd_directory* is the path to the directory where you can access the DVD.

ESD images (downloaded files)

- Navigate to the location where the installation images reside.
- Enter the following command:

```
./install
```

3 When the following message appears, press **Enter** to continue:

```
Symantec Installation Script  
Copyright 1993 - 2013 Symantec Corporation, All Rights Reserved.
```

```
Installing NetBackup Client Software
```

```
Please review the SYMANTEC SOFTWARE LICENSE AGREEMENT located on  
the installation media before proceeding. The agreement includes  
details on the NetBackup Product Improvement Program.
```

```
For NetBackup installation and upgrade information specific to your  
platform and to find out if your installed EEBs or hot fixes are  
contained in this release, check out the Symantec Operations Readiness  
Tools (SORT) Installation and Upgrade Checklist and Hot fix and EEB  
Release Auditor, respectively, at https://sort.symantec.com/netbackup.
```

```
Do you wish to continue? [y,n] (y)
```

4 Select all of the client types that you want to install and follow the installation prompts.

Installing NetBackup add-on products

After your initial installation is complete, you can install any other NetBackup add-on products (such as language packages).

How to configure the window manager for the Java Interface (NetBackup-Java compatible platforms)

Always set your window manager so that windows become active only when you click inside the windows. Do not enable auto focus, where windows become active

How to configure the window manager for the Java Interface (NetBackup-Java compatible platforms)

if you move the mouse pointer over them. The NetBackup-Java interfaces do not run properly with auto focus enabled.

Installing server software on Windows systems

This chapter includes the following topics:

- [Requirements for Windows NetBackup server installation](#)
- [About the NetBackup preinstallation Environment Checker](#)
- [Running the preinstallation Environment Checker](#)
- [Requirements for Windows cluster installations and upgrades](#)
- [Performing local, remote, or clustered server installation on Windows systems](#)
- [Post-installation tasks for NetBackup cluster environments](#)
- [Verifying Windows cluster installations or upgrades](#)
- [Installing NetBackup servers silently on Windows systems](#)

Requirements for Windows NetBackup server installation

Before you install NetBackup, make sure that your backup environment meets the following requirements:

Other backup software

Remove any other vendor's backup software currently configured on your system. The backup software of another vendor can negatively affect how NetBackup installs and functions.

OS updates	Make sure that you have applied the most current operating system patches and updates. If you are not certain that your operating system is current, contact your operating system vendor and request the latest patches and upgrades.
Storage devices	Devices such as robots and standalone tape drives must be installed according to the manufacturers' instructions and recognized by the Windows software.
Backup environment communication	Make sure that your network configuration allows all servers and clients to recognize and communicate with one another. Generally, if you can reach the clients from a server by using the ping command, the setup works with NetBackup.
Server configuration	The server system configuration should comply as follows: <ul style="list-style-type: none">■ Operating system Windows 2008 Server, Windows 2008 R2 Server, or Windows 2012/2012 R2.■ Memory Master servers in a production environment with several database agents enabled, should have a minimum of 8 GB of memory each. Media servers in a production environment with several database agents enabled, should have a minimum of 4 GB of memory each. For additional information about memory requirements, refer to the <i>NetBackup Backup Planning and Performance Tuning Guide</i>. http://www.symantec.com/docs/DOC5332■ Screen resolution Should be configured for at least 1024x768, 256 colors.
Disk space requirements	<ul style="list-style-type: none">■ An NTFS partition.■ NetBackup catalogs contain information about your backups, which become larger as you use the product. The catalog disk space requirements depend primarily on the aspects of your backup configuration. For example, the number of files that are backed up, the frequency of your backups, and how long you retain your backup data. For additional information about disk space requirements, refer to the <i>NetBackup Getting Started Guide</i>. http://www.symantec.com/docs/DOC5332

General requirements	<p>Make sure that you have all of the following items:</p> <ul style="list-style-type: none"> ■ NetBackup installation DVDs or ESD images ■ Appropriate license keys ■ Administrator account and password for all servers <p>Note: To install NetBackup on Windows 2008 Server, Windows 2008 R2 Server, Windows 2012 R2, and Windows 2012 UAC-enabled environments, you must log on as the official administrator. Users that are assigned to the Administrators Group and are not the official administrator cannot install NetBackup in UAC-enabled environments. To allow users in the Administrators Group to install NetBackup, disable UAC.</p>
Server names	<p>When you are prompted for server names, always enter the appropriate host names. Do not enter IP addresses.</p>
Mixed versions	<p>Make sure to install NetBackup servers with a release level that is at least equal to the latest client version that you plan to use. Earlier versions of server software can encounter problems with later versions of client software.</p>
CIFS-mounted file systems	<p>Symantec does not support installation of NetBackup in a CIFS-mounted directory. File locking in CIFS-mounted file systems can be unreliable.</p>
Installations on Windows 2008 Server Core	<p>You can only install NetBackup on these computers with the silent installation method.</p> <p>See “Installing NetBackup servers silently on Windows systems” on page 75.</p>
NetBackup communication	<p>NetBackup services and port numbers must be the same across the network.</p> <p>Symantec suggests that you use the default port settings for NetBackup services and Internet service ports. If you modify the port numbers, they must be the same for all master servers, media servers, and clients. The port entries are in the following file:</p> <pre>%SYSTEMROOT%\system32\drivers\etc\services</pre> <p>To change the default settings, you must perform a NetBackup custom installation of NetBackup or edit the <code>services</code> file manually.</p>
Remote Administration Console installation	<p>You must provide the names of Remote Administration Console hosts during master server installation.</p>

Remote and cluster installations

In addition to all previously stated installation requirements, the following guidelines apply to remote installations and cluster installations:

- The source system (or primary node) must run Windows 2008 Server, Windows 2008 R2 Server, or Windows 2012/2012 R2.
- The destination PC (or clustered nodes) must have Windows 2008 Server, 2008 R2 Server, or Windows 2012/2012 R2.
- The Remote Registry service must be started on the remote system.

Starting with NetBackup 7.5.0.6, the NetBackup installer can enable and start the Remote Registry service on the remote system. If the Remote Registry service is not started, the installation receives the following error message:

```
Attempting to connect to server server_name failed with the following error: Unable to connect to the remote system. One possible cause for this is the absence of the Remote Registry service. Please ensure this service is started on the remote host and try again.
```

- The installation account must have administrator privileges on all the remote systems or on all nodes in the cluster.
- All nodes in a cluster must run the same operating system, service pack level, and version of NetBackup. You cannot mix versions of server operating systems.

About the NetBackup preinstallation Environment Checker

Note: The preinstallation Environment Checker is a deprecated utility. Symantec recommends use of the SORT tool.

See “[About Symantec Operations Readiness Tools](#)” on page 11.

<https://sort.symantec.com/netbackup>

Starting with NetBackup 7.1, an Environment Checker is included to help identify any problems that may prevent a successful NetBackup server installation or upgrade. The Environment Checker is currently only available for Windows.

The Environment Checker is available as a link on the DVD browser. The checker is a standalone function that you run before an installation or an upgrade.

The Environment Checker provides you with the following abilities:

- Assess a system to determine if it is ready for a new NetBackup installation or upgrade.
- Perform the assessment on local and remote Windows systems.
- Create a list of remote computers to check, either manually or by browsing the network.
- Run the Environment Checker on all supported Windows platforms that support NetBackup as a master server or a media server (x86 and x64).
- Generate HTML reports for immediate viewing.

See [“Running the preinstallation Environment Checker”](#) on page 57.

Running the preinstallation Environment Checker

Note: The preinstallation Environment Checker is a deprecated utility. Symantec recommends us of the SORT tool.

See [“About Symantec Operations Readiness Tools”](#) on page 11.

<https://sort.symantec.com/netbackup>

Use the following procedure to run the Environment Checker and assess whether computers are ready for NetBackup installation.

To run the Environment Checker

- 1 Start the NetBackup Installation Wizard with one of the following methods:
 - DVD media
Insert the NetBackup for Windows DVD in the drive. If Autorun is disabled, navigate to the DVD drive and run `Browser.exe`.
 - ESD images (downloaded files)
Navigate to the directory where the images reside and run `Browser.exe`.
- 2 On the **Home** screen, click **Preinstallation**.
- 3 On the **Preinstallation** screen, click **Run the preinstallation Environment Checker**.
- 4 On the **Welcome** screen, review the content and click **Next**.
- 5 On the **Choose** screen, select the systems to check as follows:

Local Environment Check (default) To check the local computer only, leave this option checked and click **Next**.

After the computer check has completed, a summary page appears that describes the results.

Remote Environment Check ■ To check one or more remote computers, select this option and click **Next**.

Note: You can keep the **Local Environment Check** option to include the local computer. You can also deselect this option to exclude it.

■ On the **Remote** screen, add or remove computers to check as follows:

■ **Add Server From List**

Click this option to select a computer from a list of available systems on your network. Then click **Next**.

Enter the appropriate **User Name** and **Password** for the selected computer, then click **OK**.

■ **Add Server Manually**

Click this option to add computer names manually.

On the **Manual Remote Computer Selection** dialog box, enter the appropriate **Domain Name** and the **Server Name**, then click **OK**.

On the **Remote Computer Login Credentials** dialog box, enter the appropriate **User Name** and **Password**, then click **OK**.

■ **Remove**

To remove a computer from the **Remote Computers** list, select the computer from the list and click **Remove**.

■ After all computers that you want to check are added to the **Remote Computers** list, click **Next**.

The Environment Checker performs a validation process for each remote computer. After all have been completed, click **Next** to start the check on all listed computers.

- 6 When all computers have been checked, the **Results** screen displays a list of the checked systems with a brief result under each computer name. Click on a computer name to see the complete results for that computer. The following describes the symbols that may appear in a summary:

Green check mark	Indicates that the item meets the requirements for a NetBackup installation or an upgrade.
Yellow exclamation point	Indicates that a potential issue has been detected that may, or may not cause a problem for a NetBackup installation or an upgrade.
Red X	Indicates that the item does not meet the NetBackup installation requirements. Any summary report items with a red X must be corrected before you attempt a NetBackup installation or an upgrade.

Note: Symantec recommends that you address all items that are marked with a yellow exclamation point and a red X. Then run the Environment Checker again.

- 7 To save the results file, do one of the following:
- To save the results file to the default location, leave the check mark for the **Save Results To** check box.
 - To save the results file to a different location, click **Change Path**, enter the appropriate location, then click **Save**.

If you do not want to save the results file, click the **Save Results To** check box to remove the check mark.

- 8 To exit from the Environment Checker, click **Finish**.

See [“About the NetBackup preinstallation Environment Checker”](#) on page 56.

See [“About Symantec Operations Readiness Tools”](#) on page 11.

Requirements for Windows cluster installations and upgrades

In addition to the normal server requirements, NetBackup cluster installations require special considerations.

The following describes the guidelines for NetBackup cluster installations and upgrades on Windows systems:

Server operating system	The source and the destination systems must run Windows 2008, 2008 R2, 2012, or 2012 R2 Server.
Privileges	To perform clustered installations, you must have administrator privileges on all of the remote nodes in the cluster. Symantec recommends that you keep a record of all nodes in the cluster and what software exists on each node.
NetBackup virtual name and IP address	Have the virtual name and IP address for NetBackup available. You must provide this information during installation.
Operating system on nodes	All clustered nodes must use the same operating system version, service pack level, and NetBackup version. You cannot run mixed server versions in a clustered environment.
Cluster support changes for media servers	Beginning with NetBackup 7.1, you cannot perform a new installation of a clustered media server. You can, however, upgrade existing 6.x clustered media servers to NetBackup 7.7.1 and still keep them clustered.
Windows Server Failover Clusters (WSFC)	<ul style="list-style-type: none"> ■ The shared disk that the NetBackup Group uses must already be configured in the cluster and online on the active node. ■ Install NetBackup from the node with the shared disk (that is, the active node). ■ Computer or host names cannot be longer than 15 characters.
VCS clusters	<ul style="list-style-type: none"> ■ For SFW-HA 4.1 and SFW-HA 4.2: Make sure that you install the patch from the following website before you install versions 7.x or upgrade from versions 6.x: http://entsupport.symantec.com/docs/278307 ■ All NetBackup disk resources must be configured in Veritas Enterprise Administrator (VEA) before you install NetBackup.

Cluster node device configuration and upgrades

When you upgrade clusters, the `ltid` and the robotic daemons retrieve the device configuration for a particular cluster node from the EMM database. The cluster node name (provided by `gethostname`) stores or retrieves the device configuration in the EMM database. The cluster node name is used when any updates are made to the device configuration, including when `ltid` updates the drive status. The cluster node name is only used to indicate where a device is connected. The NetBackup virtual name is employed for other uses, such as the robot control host.

Performing local, remote, or clustered server installation on Windows systems

Use the following procedure to perform a local, a remote, or a clustered install of NetBackup on a Windows computer.

To install NetBackup 7.7.1 server software on a local, remote, or clustered Windows server

- 1 Log on to the system. Be sure to log on with administrator privileges.
 - For local installations, log on to the system where you want to install NetBackup.
 - For remote installations, log on to a system with network access to all of the hosts where you want to install NetBackup.
 - For cluster installations, log on to the active node (the node with the shared disk).
- 2 Start the NetBackup Installation Wizard with one of the following methods:
 - DVD media
Insert the NetBackup for Windows DVD in the drive. If Autorun is disabled, navigate to the DVD drive and run `Browser.exe`.
 - ESD images (downloaded files)
Navigate to the directory where the images reside and run `Browser.exe`.
- 3 On the initial browser screen (**Home**), click **Installation**.
- 4 On the **Installation** screen, click **Server Software Installation**.
- 5 On the **Welcome** screen, review the content and click **Next**.
- 6 (Conditional) If you previously installed NetBackup 7.7.1 on this host, you see the **Program Maintenance** dialog.

- Select **Modify** to change installation settings for the local host, or to use the local host as a platform to perform push installation to remote hosts.
 - Select **Repair** to restore NetBackup 7.7.1 to its original state on the local host.
 - Select **Remove** to remove NetBackup 7.7.1 from the local host.
- 7 On the **License Agreement** screen, do the following:
- **I agree to and accept the terms of the license agreement.**
You must select this item to install the software.
 - **Participate in the NetBackup Product Improvement Program.**
By default, this option is enabled. To disable this option, click the check box to remove the check mark.
 - Click **Next**.
- 8 On the **Symantec NetBackup Installation Type** screen, provide the following information:
- | | |
|-------------------------|--|
| Where to install | <ul style="list-style-type: none">■ For a local installation, select Install to this computer only.■ For a remote installation, select Install to multiple computers on your network.■ For a cluster installation, select Install a clustered Master Server.
This option is available only if the installation process determines that your system is configured for a Windows Server Failover Cluster (WSFC) or VCS clustered environment. |
| Typical | Select this option to install NetBackup with the default settings. |
| Custom | Select this option to install NetBackup with the settings that you want. |
- Click **Next**.
- 9 On the **NetBackup License Key and Server Type** screen, provide the following information:

License Key

Enter the base product license key that you received with your product.

The license key that you provide determines which components you can select. For example, you can click the icon next to **NetBackup Master Server** only if you enter a master server license key.

For remote and cluster installations:

Note: The license key that you enter here gets pushed to the other nodes. Your license key may enable add-on products. If you push NetBackup to nodes that have an add-on product already installed, your key works for the add-on product(s).

During this installation process, the following occurs to verify that you have proper credentials to perform remote installations:

- When you select a clustered system for installation, NetBackup determines if you have proper administrator credentials on all nodes in the cluster. If you do not have the proper credentials, the system is not added to the list.
- If you have the proper credentials, NetBackup performs a second check to determine if a license key is needed. If a key is needed and one was not entered, the system cannot be added to the list. You must enter a valid license key to install on that node. If you enter an invalid license key, this screen remains visible until a valid key is entered.

NetBackup Master Server

Click this icon to install master server software.

NetBackup Media Server

For local or remote installations, click this icon to install media server software.

- 10 (Conditional) This step applies only to the local installations that are **Custom**. For **Typical** installations, skip to the next step.

This step describes how to select and configure the **NetBackup Installation Folder**, **NetBackup Port Numbers**, and the **NetBackup Services**.

■ **NetBackup Installation Folder**

On this screen, you can select where the NetBackup files are installed.

Destination Folder

By default, NetBackup files are installed to the following location:

C:\Program Files\VERITAS

To change the folder destination where NetBackup is installed:

- Click **Change**.
- Browse to the preferred location and designate a new or an existing folder.
- Click **Next**.

Additional information about installation folder restrictions is available.

See [“Restrictions on the NetBackup installation directory”](#) on page 10.

Click **Next**.

■ **NetBackup Port Numbers**

On this screen, you can change port numbers, if it is necessary in your configuration.

You may need to change a port number if you encounter conflicts when NetBackup and another industry product try to share the same port. Another example is if a port conflict occurs with a firewall, which may cause security issues.

To change a port number, select the port number that you want to replace and type the new number.

Click **Next**.

■ **NetBackup Services**

On this screen, provide the following startup account and startup type information for NetBackup services:

Log On

Specify either **Local System account** or **This account**.

By default, the **Local System account** is selected, so that NetBackup uses the built-in system account. When this option is selected, the fields below it are disabled.

To specify a different account:

- Select **This account**.
- Enter the account information in the following fields:

Domain

Username

Password

Startup Type

This option determines whether NetBackup services start automatically if you need to restart the NetBackup host. The default is **Automatic**.

To start NetBackup services manually after a restart, select **Manual**.

Start job-related NetBackup services following installation

By default, job-related services are set to start automatically after the installation has completed.

To prevent job-related services from starting automatically, click on the box to clear the check mark.

Safe Abort Option

This option determines how the installation proceeds if a restart is required as part of the installation.

If you select this option and the installation process determines that a restart is required, the installation stops. The system is then rolled back to its original state.

If you do not select this option, the installation proceeds even if the installation process determines that a restart is required.

Click **Next**.

11 On the **NetBackup System Names** screen, provide the following information:

Master Server Name (Conditional) For local master server installations, enter the name of the local computer. For a cluster installation, enter the cluster virtual server name.

For media server installations, you must change the name to the master server name to which the media server is configured.

Additional Servers Enter the names of any additional NetBackup master servers and media servers that you want to communicate with this server. Include the names of computers where you plan to install NetBackup later. To enter more than one name, separate each name with a comma or press **Enter** after each name.

Media Server Name This field appears only for local NetBackup Enterprise media server installations.

When you install media server software, this field defaults to the local server name.

EMM Server Name The EMM (Enterprise Media Manager) server contains all of the information about NetBackup volume configuration and device configuration.

Accept the default name of the EMM server. Starting with NetBackup 7.6 you must configure EMM on the master server. All master servers must have their own EMM configuration. Remote EMM or shared EMM is no longer supported in NetBackup 7.6.

Consider the following in regard to the EMM server:

- Symantec does not support EMM server installation on a CIFS-mount.
- If the NetBackup system shares drives by using the Shared Storage Option (SSO), all NetBackup servers must use the same host to store device information.

For more information on EMM servers and EMM databases, refer to the *NetBackup Administrator's Guide, Volume I*.

<http://www.symantec.com/docs/DOC5332>

OpsCenter Server Name (Optional)

OpsCenter is a web-based administration and management tool for NetBackup.

If you have an OpsCenter server or plan to install one, enter the server name or the IP address for that server here.

For a clustered server, do not use the virtual name. Instead, use the actual host name of the cluster node.

Click **Next**.

12 (Conditional) For remote installations only:

On the **Symantec NetBackup Remote Hosts** screen, specify the hosts where you want NetBackup installed.

- **Windows Destination Systems**

Right-click **Windows Destination Computers** and select from the drop-down menu, or use the following methods:

- Browse**

Click here to search the network for the hosts where you want to install NetBackup.

- On the **Available Systems** dialog box, select the computer to add and click **Next**.
- On the **Remote Computer Login Credentials** dialog box, enter the **User Name** and the **Password** of the account to be used to perform the installation on the remote computers.
- If you plan to install to multiple remote computers, click the box next to **Remember User Name and Password**. Selecting this option prevents the need to enter this information for each remote computer.
- Click **OK**.
- On the **Remote Destination Folder** dialog box, verify or change the **Destination Folder** where NetBackup is installed.

The default location is C:\Program Files\Veritas.

If you plan to install to multiple remote computers and you want to use the same location, click the box next to **Use this folder for subsequent systems**. Selecting this option prevents the need to enter the location for each remote computer.

Import Click here to import a text file that contains a list of host names. When you create the text file, the host names must be defined in the following format:

Domain\ComputerName

Add Click here to add a host manually.

- On the **Manual Remote Computer Selection** dialog box appears, enter the **Domain** and the **Computer Name**, then click **OK**.
- On the **Remote Computer Login Credentials** dialog box, enter the **User Name** and the **Password** of the account to be used to perform the installation on the remote computers.

If you plan to add and install to multiple remote computers, click the box next to **Remember User Name and Password**. Selecting this option prevents the need to enter this information for each remote computer.

- Click **OK**.
- On the **Remote Destination Folder** dialog box, verify or change the **Destination Folder** where NetBackup is installed.

The default location is C:\Program Files\Veritas\.

If you plan to install to multiple remote computers and you want to use the same location, click the box next to **Use this folder for subsequent systems**. Selecting this option prevents the need to enter the location for each remote computer.

- Click **OK**.

Remove To remove a host from the **Destination Systems** list, select the host and click here.

Change Click here to change the destination for NetBackup file installation on the selected remote host.

- Click **Next**.

13 (Conditional) For cluster installations only:

On the **NetBackup Remote Hosts** screen, specify the remote system information for installation on those computers.

- On the initial screen, right-click **Browse**.

Performing local, remote, or clustered server installation on Windows systems

- On the **Available Systems** dialog box, select the computer that you want to add. Control-click to select multiple computers.

Click **Next**.

- On the **Remote Computer Login Credentials** dialog box, enter the user name, password, and domain that NetBackup is to use on the remote system(s).

If you intend to add more remote computers, click the check box next to **Remember user name and password**.

When you provide credentials, you select cluster nodes and add them to the **Windows Destination Systems** list. These are the nodes on which you remotely install NetBackup. Make sure that you select your local host when you select systems to install.

Each time you choose a system, NetBackup performs system and license checks. For example, it verifies the system for a server installation that matches the type that you selected, as follows:

- | | |
|---|--|
| ■ NetBackup not installed | Considers the remote to be verified. |
| ■ NetBackup already installed | Compares the installation type on that system to the installation type that you request. |
| ■ Invalid combination | Notifies you of the problem and disallows the choice. One example of an invalid combination is to try to install a Remote Administration Console on a remote system that is already a master server. |
| ■ Remote system not a supported platform or level | Notifies you of the problem and disallows the choice. |

The installation procedure also verifies that you have proper administrator credentials on the remote system. If you do not have administrator credentials, the **Enter Network Password** screen appears, and prompts you to enter the administrator's user name and password.

Click **OK** and continue selecting destination systems.

This process repeats for each node that you select. You can elect to retain the user name and password. In that case, you are prompted only when the user name or password is not valid.

Note the following about the push-install process in a clustered environment:

- You can install NetBackup on any number of nodes. However, the clustering service sets the limit for the number of nodes in a cluster, not NetBackup.

- Language packages and other NetBackup add-on products cannot be installed with the push method. Add-on products must be installed on each individual node in the cluster group. For instructions on how to install these products, refer to the NetBackup documentation that supports each product.
- NetBackup pushes to the other nodes only the license key you enter at the beginning of the installation. Your license key may enable add-on products. If you push NetBackup to nodes that have an add-on product already installed, your key works for that product.

Click **Next**.

14 (Conditional) For cluster installations only:

On the **Cluster Settings** screen, you provide the virtual and the physical network information.

For new installations, the following configuration settings that you enter apply to all nodes:

Create a new Cluster Group For new cluster installations, select this option.

IPv4 Clusters The default cluster setting is IPv4.
 Enter the following addresses:

- **Virtual IPv4 Address**
 The IP address to which the virtual server name should resolve.
 For new cluster installations, you must enter the address manually.
- **IPv4 Subnet Mask**
 Identifies a subnetwork so that IP addresses can be shared on a local area network. This number correlates directly to the virtual IP address of the cluster.

IPv6 Clusters To enable IPv6 clusters, select this option.
 Enter the following IP address:

- **Virtual IPv6 Address**
 The IPv6 address must be entered in CIDR format.

NB Cluster Group Name The name that is used to identify a NetBackup service group or resource group. The resources in any resource group are related and interdependent.

Virtual Host Name	<p>The name by which NetBackup is known in the cluster.</p> <p>When you install the client software, this host name must be added to the Additional Servers field on the NetBackup System Names screen.</p> <p>The server uses this name when it communicates with the client nodes.</p>
Path to Shared Data	<p>A directory on one of the shared disks in the cluster where NetBackup stores configuration information. If the letter for the disk (or drive) does not appear in the pull-down list, enter only the letter.</p>
Public Network	<p>For NetBackup clustered environments, select a public network that is assigned to the node of the cluster.</p> <p>Warning: You must not select a private network that is assigned to this cluster.</p>
Cluster Configuration	<p>After you set all of the parameters, click this icon to configure the cluster for use with NetBackup. The Next icon is not available until after successful cluster configuration.</p> <p>The text box provides the following information about the configuration:</p> <ul style="list-style-type: none">■ Identifies any existing clusters or NetBackup cluster groups.■ Indicates a successful configuration.■ Identifies any problems or errors that occurred during the configuration (configuration failure). <p>Note: If you click Cancel after a successful cluster configuration for new installations, a pop-up message appears. The message asks if you are sure that you want to proceed with the cancelation. To cancel the installation and remove the new cluster group, click Yes. To continue with the installation and retain the new cluster group, click No and then click Next.</p> <p>If the cluster configuration fails, see the <i>NetBackup Clustered Master Server Administrator's Guide</i> for information about how to resolve the problem.</p> <p>http://www.symantec.com/docs/DOC5332</p>

When the successful cluster configuration message appears, click **Next**.

- 15 On the **Ready to Install the Program** screen, review the **Installation Summary** that shows your selections from the previous steps.

Note: Symantec recommends that you review the summary screen for any warning messages. You can prevent installation and upgrade issues if you resolve any problems before you continue the installation.

Then select one of the following options:

- Click **Install** to start the installation.
- Click **Back** to view the previous screens and make any changes, then return to this screen and click **Install**.
- Click **Cancel** to cancel the installation.

After you click **Install**, the installation process begins and a screen appears that shows you the installation progress. This process may take several minutes.

For remote and cluster installations, up to five installations occur simultaneously. When an installation is completed, another one begins so that a maximum of five installations are in progress.

16 On the **Installation Complete** screen, select from the following options:

Add Keys

(Conditional) For local installations only, Symantec recommends that you enter additional license keys now for any other NetBackup products you plan to install.

- To enter additional license keys, click **Add Keys**.
- When the list of **Current License Keys** appears, click **Add Key** to enter a new license key, then click **Add**.
- After all license keys are entered, close the **Current License Keys** window.

View installation log file

The installation log file provides detailed installation information and shows whether any errors occurred.

Examine the installation log at the following location:

```
%ALLUSERSPROFILE%\Symantec\  
NetBackup\InstallLogs\
```

Note: When you perform a remote or a cluster installation to multiple computers, this option only lets you view the log for the local computer. Each computer that you selected for installation contains its own installation log file. To view the log file of a remote computer, open a Windows Explorer window and enter \\<COMPUTERNAME>.

Search the installation log for the following error indications:

- Strings that include `Return Value 3`.
- Important log messages that are color coded as follows:
 Yellow = warning.
 Red = error.

Finish

Select one of the following to complete the installation:

- If you are done installing software on all servers, click the box next to **Launch NetBackup Administration Console now** and click **Finish**. The NetBackup Administration Console starts a Configuration Wizard so that you can configure your NetBackup environment.
- If you have more server software to install, click **Finish**. You can move on to the next computer and install the necessary server software.

17 Repeat the steps in this procedure for any other servers.

18 After all server software is installed, you are ready to install client software.

See [“About NetBackup client installation”](#) on page 85.

See [“Post-installation tasks for NetBackup cluster environments”](#) on page 74.

See [“Verifying Windows cluster installations or upgrades”](#) on page 74.

Post-installation tasks for NetBackup cluster environments

After NetBackup server software is installed in a cluster, note the possible actions you may need to take:

Restart	You may need to restart each of the cluster nodes after the installation is complete.
WSFC and VCS clusters	<p>Under normal circumstances, cluster configuration is one of the final steps when you install NetBackup in a cluster. If this step is not done or does not complete successfully, you can use the <code>bpclusterutil</code> command from the active node to perform this step.</p> <p>For information on how to run <code>bpclusterutil</code>, see the <i>NetBackup Commands Reference Guide</i>.</p> <p>http://www.symantec.com/docs/DOC5332</p>
WSFC clusters	Any NetBackup resources that you took offline come back online automatically.

See “[Verifying Windows cluster installations or upgrades](#)” on page 74.

Verifying Windows cluster installations or upgrades

The Cluster Administration console lets you verify the installation or upgrade and view your current system structure.

To verify a successful WSFC cluster installation or upgrade through the Cluster Administration console

- 1 During a cluster installation, you can open the Cluster Administration console to see your current structure.
- 2 After you have completed the installation and the configuration process, the console shows the new cluster group configuration.

To verify a successful VCS cluster installation or upgrade through the Cluster Manager console

- 1 During a cluster installation, you can open the Cluster Administration console to see your current structure.
- 2 After you have completed the installation and the configuration process, the console shows the new cluster group configuration.

See [“About NetBackup server configuration”](#) on page 116.

Installing NetBackup servers silently on Windows systems

A silent installation avoids the need for interactive input in the same manner as performing a remote installation. Silent NetBackup installations are not supported if you want to run the NetBackup services as a specific user rather than the local system.

To perform a silent installation, you must first modify the appropriate NetBackup script. After script modification, you can run the script to initiate the silent installation.

Note: For Windows 2008 Server Core systems, you can only install NetBackup with this procedure.

To install NetBackup server software silently

- 1 Log on as administrator to the system where you want to install NetBackup.
- 2 Insert the NetBackup installation DVD or navigate to the location where the ESD images (downloaded files) reside.
- 3 Open Windows Explorer and copy the contents of the X86 or the X64 directory to a temporary directory on your hard drive. Choose the directory that is associated with the platform type that you want to install.
- 4 Since the source files are read-only, you must change the permissions for the copied files to allow the installation or the update.
- 5 In the temporary directory where the copied files reside, select the appropriate script to modify:
 - To install a master server, edit `silentmaster.cmd`
 - To install a media server, edit `silentmedia.cmd`
 - To install a NetBackup Remote Administration Console, edit `silentadmin.cmd`
- 6 Edit the following lines as needed for your installation:
 - `SET ADDITIONALSERVICES=media1,media2,media3`

Enter the names of any additional NetBackup master servers and media servers that you want to communicate with this host. Include the names of servers where you plan to install NetBackup later.

If no other servers are to communicate with this host, remove this line from the script.

- `SET ABORT_REBOOT_INSTALL=0`

This line lets you determine how you want the installation to continue if a restart is required. Select from the following settings:

0 (zero, default)

By default, a silent installation does not abort if it is determined that a restart is required. If you leave this setting at 0, select one of the following tasks:

- After the installation is complete, check the installation log to see if a restart is required. If the string **in use** appears anywhere in the log, you must restart the system manually.
- Force an automatic restart after the installation is complete.

To force an automatic restart, before you run the script, remove the following option from the silent installation command script (`silent*.cmd`):

```
REBOOT="ReallySuppress"
```

Warning: A forced restart occurs with no warning to the user. It does not cancel the installation or roll back the system to its original state.

1 (one)

Select this setting to abort the installation if it is determined that a restart is required.

If a restart is needed, this setting cancels the installation and the system is rolled back to its original state.

7 Save the script and run it.

8 Examine the installation log at the following location:

```
%ALLUSERSPROFILE%\Symantec\NetBackup\InstallLogs\
```

Search the installation log for the following error indications:

- Strings that include `Return Value 3`.
- Important log messages are color coded as follows:
 - Yellow = warning.
 - Red = error.

After all server software is installed, you are ready to install client software.

See [“About NetBackup client installation”](#) on page 85.

Installing administrative interface

This chapter includes the following topics:

- [About the NetBackup Remote Administration Console](#)
- [About the NetBackup Administration Console](#)

About the NetBackup Remote Administration Console

The NetBackup Remote Administration Console is an interface-only version of NetBackup that you can use to administer NetBackup servers from another computer. The computer that runs the NetBackup Remote Administration Console does not require NetBackup software.

The following is a brief description of the NetBackup Remote Administration Console operation:

- The console lets you perform all NetBackup operations exactly like the NetBackup Administration Console on a local NetBackup server. You can create backup policies, manage volumes, view status, monitor tape drives, and perform other operations.
- The console displays the name of the server it administers, rather than a local host name.
- The console can only administer other NetBackup servers. It cannot act as a master or a media server.

Installing the NetBackup Remote Administration Console

Installation is a two-step process as follows:

- Install the NetBackup Remote Administration Console.
- Add the NetBackup Remote Administration Console host name to the server list of the hosts that you want to administer.
You must also add the host names of the servers that you want to administer to the server list on the host where you install the remote console.
The following table shows an example of the required server list entries for each host. RAC1 refers to the Remote Administration Console.

Host name	Required server list entries
Master1	RAC1
Media1	RAC1
Media2	RAC1
RAC1	Master1, Media1, Media2

Note: You cannot install NetBackup Remote Administration Console on a computer where NetBackup server software is already installed.

To install the NetBackup Remote Administration Console

- 1 On the computer where you want to install the remote administration console, do one of the following:
 - Insert the appropriate DVD that contains the NetBackup software.
On Windows systems with Autorun enabled, the installation starts automatically.
On Windows systems with Autorun disabled, navigate to the DVD directory and run `Browser.exe`.
 - Navigate to the location where the downloaded files reside and run `Browser.exe`.
- 2 On the initial screen, select **Installation**.
- 3 On the **Installation** screen, click **NetBackup Administration Console Installation (x64 only)**.
- 4 On the **Welcome** screen, review the content and click **Next**.
- 5 On the **License Agreement** screen, accept the agreement and click **Next**.
- 6 On the **NetBackup Installation Type** screen, select **Install to this computer only** and **Typical Installation** and then click **Next**.

If an earlier version of the console already exists, you have the following options:

- Cancel the installation and remove the earlier version of the console. Then run the 7.7 console installation again.
 - Specify an alternate installation location for the 7.7 version of the console.
- 7 On the **Ready to Install the Program** screen, review the Installation Summary and click **Install**.
 - 8 On the **Installation Complete** screen, click **Finish**.
 - 9 To open the console, click **Start > Programs > Symantec NetBackup > NetBackup Remote Admin Console**.

Note: Installing NetBackup Remote Administration console installs multiple versions of remote administration consoles. For example, when you install the remote administration console version 7.7, NetBackup Remote Administration Consoles for version 7.0 through 7.7 are all installed.

Configuring server lists for the NetBackup Remote Administration Console

The following methods are available to configure server lists for the NetBackup Remote Administration Console:

- Use the NetBackup Administration Console
- On UNIX servers, edit the `bp.conf` file.
- On Windows servers, edit the system registry.

To configure server lists for the NetBackup Remote Administration Console by using the NetBackup Administration Console

- 1 On the **NetBackup Administration Console** in the left pane, click **Host Properties > Master Servers**.
- 2 In the **Master Servers** window in the right pane, right-click the name of the host server and select **Properties**.
- 3 In the **Master Server Properties** window, click the **Servers** icon from the tree in the left pane.
- 4 In the **Servers** window, click **Add**.
- 5 Enter the name of the host that is to run the NetBackup Remote Administration Console.

- 6 Click **Add**. The name of the host appears in the **Additional Servers** list.
- 7 Click **Close** and **OK**.

To configure server lists for the NetBackup Remote Administration Console by editing the bp.conf file on UNIX servers

- 1 Log in to the master server as root.
- 2 Edit the following file:

```
/usr/opensv/netbackup/bp.conf.
```

- 3 At the end of the `SERVER =` lines, add the following line:

```
SERVER = Remote-Administration-Console-machine-name
```

The `Remote-Administration-Console-machine-name` is the name of the computer where you installed the NetBackup Remote Administration Console.

To configure server lists for the NetBackup Remote Administration Console by editing the system registry on Windows servers

- 1 Log on to the master server as the administrator.
- 2 Click **Start > Run...**
- 3 Enter `regedit.exe` and click **OK**.
- 4 In the **Registry Editor** window, locate the following file:

```
HKEY_LOCAL_MACHINE\SOFTWARE\VERITAS\NetBackup\CurrentVersion\Config
```
- 5 In the right pane, double-click on **Server**.
- 6 In the **Edit Multi-String** window, enter the name of the Remote Administration Console host and click **OK**.
- 7 Close the **Registry Editor** window.

Adding remote servers to administer from an existing NetBackup Remote Administration Console

If you have an existing NetBackup Remote Administration Console installed and you want to add a remote master server to administer, use this procedure.

To add a remote server to administer from an existing NetBackup Remote Administration Console

- 1 Log on to the host where the NetBackup Remote Administration Console is installed, and open the console.
- 2 In the left pane of the NetBackup Remote Administration Console, select **Host Properties > Master Server**.

- 3 In the **Master Servers** window in the right pane, right-click the name of the host server and select **Properties (Read/Write)**.
- 4 In the **Master Server Properties** window, click the **Servers** tab.
- 5 In the **Global Operations** field, in the **Add to all lists** field, enter the host name. Make sure that you enter the name of the host that is to run the NetBackup Remote Administration Console.
- 6 Click the **+** icon (the name of the host appears in the **Additional Servers** list), then click **OK**.

About the NetBackup Administration Console

The NetBackup Administration Console can be used to administer one or more UNIX or Windows NetBackup servers. It provides all of the standard NetBackup server interfaces. The console can be used to create backup policies, manage volumes, view status, monitor tape drives, and other operations.

NetBackup Administration Console is installed when you install or upgrade NetBackup server packages.

Installing the NetBackup Java Administration Console

You do not need to install NetBackup Administration Console separately. When you install or upgrade the master server, multiple versions of the NetBackup Java Administration Console are installed by default. For example, when you install or upgrade to NetBackup 7.7, versions 7.0 through 7.7 of the console are all installed.

Note: Symantec recommends that after you install or upgrade NetBackup server software, you should uninstall older versions of the Remote Administration Console (Windows and Java) present on the host. If the native NetBackup Administration Console for Windows is present, it is automatically uninstalled when you install or upgrade the NetBackup server software.

Use the following guidelines when you install version 7.7 of the console:

- Install the console from the NetBackup DVD for Windows or from the ESD (downloaded) files.
- Any computer that runs the console should have at least 512 MB of physical memory.

Installing or removing multiple versions of the NetBackup-Java Administration Console on Windows

A NetBackup environment may contain multiple servers with multiple NetBackup versions. You can install and remove multiple versions of the NetBackup-Java Administration Console.

Installing multiple versions of the NetBackup-Java Administration Console on Windows

To install multiple versions of the NetBackup interface in a mixed version environment, note the following restrictions and guidelines:

Updates	Only the most recent version of the NetBackup-Java Administration Console can be updated (or patched).
<code>auth.conf</code> file	<p>The NetBackup-Java Capabilities Authorization configuration file (<code>auth.conf</code>), must always be located in <code>install_path\java</code>. For example, <code>C:\Program Files\Veritas\java</code>. The file must exist there regardless of how many versions of the console are installed, or in which directories they are installed.</p> <p>The file is only used for administering NetBackup on this Windows host, and default settings exist if the file is not present. For more information about these defaults, see the section "Authorizing NetBackup-Java users" in the <i>NetBackup Administrator's Guide, Volume I</i>.</p> <p>http://www.symantec.com/docs/DOC5332</p>
Console version location	You must install each Java console version to a different folder.

To install earlier versions of the NetBackup-Java Administration Console

- 1 Insert the appropriate version NetBackup Windows installation media with the NetBackup-Java Administration Console that you want to install.
- 2 Select one of the following consoles, based on the NetBackup version:
 - For NetBackup 6.0 versions, select **NetBackup Installation** and click **Install Java Administration Console**. Select whether you want to install the 32-bit or the 64-bit console.
 - For NetBackup 6.5 versions, select **NetBackup Installation** and click **Install Java Windows Administration Console**. Select whether you want to install the 32-bit or the 64-bit console.

- For NetBackup 7.0 and 7.1 versions, select **Installation** and click **Java Windows Administration Console Installation**.
- 3 If a different version of the Java console has already been installed, specify a new folder location to prevent overwriting the earlier installation.

For example, specify `C:\Program Files\Veritas\nbjava65` for version 6.5 Java consoles.
 - 4 To complete the installation, click **Finish**.

Removing earlier versions of the NetBackup-Java Administration Console on Windows

In some cases, you can remove earlier versions of the NetBackup-Java Administration Console by using the **Add/Remove Programs** feature. You can use this method if the version that you want to remove appears in the list of programs.

If the version that you want to remove does not appear in the list of programs, you must manually remove it. Use the following procedure.

To manually remove earlier versions of the NetBackup-Java Administration Console

- 1 Remove the folder where the earlier version NetBackup-Java Administration Console is installed.
- 2 Remove the appropriate menu item from the **Start > Programs > NetBackup** menu.
- 3 Remove any relevant desktop shortcuts.

Installing NetBackup client software

This chapter includes the following topics:

- [About NetBackup client installation](#)
- [About NetBackup client installation on Windows](#)
- [About NetBackup client installation on UNIX/Linux](#)

About NetBackup client installation

By definition, NetBackup servers are also clients. When you install NetBackup server software, client software is also installed.

When you install client software, you perform a true client installation since no server software is installed.

Client software can be installed locally at each individual computer or remotely. The operating system determines which clients can be installed remotely.

Windows

A Windows host can only push client software to Windows clients.

NetBackup does not need to be installed on the host that is used to perform the remote client installation.

UNIX or Linux

A NetBackup UNIX or Linux server can only push client software to UNIX or Linux clients.

NetBackup software and client type software must be installed on the server that is used to perform the remote client installation.

About NetBackup client installation on Windows

The NetBackup client installation wizard for Microsoft Windows lets you select the appropriate setup and installation options from a series of wizard screens. After you select options, a window appears that lets you verify your selections before the installation begins.

While the installation is in progress, a dialog box provides details of the installation and the setup progress. When the installation is completed, a final window shows the results.

Note the following when you install NetBackup client software on Windows systems:

Client installation restrictions You cannot install NetBackup client software on the computers that currently have NetBackup server software. In these cases, you must first remove the NetBackup server software.

See ["Removing NetBackup server software on Windows systems"](#) on page 137.

See the *NetBackup Installation Guide for Windows*.

<http://www.symantec.com/docs/DOC5332>

User permissions

- By default on Windows 2008, 2008 R2, 2012, and 2012 R2 Server systems, only administrators have write permission to the `Program Files` directory.
- NetBackup writes log files and progress files to the following location:

`Program Files\VERITAS\NetBackup\Logs`

To perform backups and restores with the Backup, Archive, and Restore interface, users must have write permission to the `Logs` directory. Users without write permission to this directory receive an error message, and the backup or restore is canceled. The administrator account has write permission by default, but you must ensure that other users also have write permission.

About Windows client installation methods and requirements

You can install NetBackup clients on Windows systems with the following methods:

Table 6-1 Installation methods and requirements

Method	Requirements	Details
Local installation	<p>To install NetBackup client software locally, the system must meet the following configuration requirements:</p> <ul style="list-style-type: none">■ Microsoft Windows XP, Windows 2008/Vista, Windows 2008 R2/Windows 7, or Windows 2012/2012 R2/Windows 8■ Any TCP/IP transport that is Windows Sockets compliant. (Use of the TCP/IP transport that comes with the server or the operating system is recommended.)■ A network adapter that your TCP/IP transport supports	<p>The installation wizard installs the client software only on the computer where you run the installation.</p> <p>See “Installing NetBackup Windows clients locally or remotely” on page 89.</p>

Table 6-1 Installation methods and requirements (*continued*)

Method	Requirements	Details
Remote installation	<p>To install NetBackup client software remotely, the system must meet the following configuration requirements:</p> <ul style="list-style-type: none"> ■ All the requirements for local installations must be met. ■ The source system must run Windows 2008, 2008 R2, 2012, or 2012 R2 Server. ■ Administrator privileges are required for the user that performs remote installations. ■ Remote Registry service must be started on the remote system. If the Remote Registry service is not started, the installation receives this error message: <pre>Attempting to connect to server server_name failed with the following error: Unable to connect to the remote system. One possible cause for this is the absence of the Remote Registry service. Please ensure this service is started on the remote host and try again.</pre>	<p>The installation wizard scans the network for available clients where you can install the client software.</p> <p>The source computer must run Windows 2008, 2008 R2, or 2012 Server.</p> <p>Also, a remote installation requires system administrator privileges.</p> <p>Note: You cannot install clients remotely from NetBackup Windows servers to UNIX computers.</p> <p>See “Installing NetBackup Windows clients locally or remotely” on page 89.</p>
Silent installation	<p>The requirements for silent installation are the same as the requirements for a local installation.</p>	<p>A silent installation is a process that does not require interactive input. However, you must edit the <code>silentclient.cmd</code> file before you run it.</p> <p>See “Installing NetBackup Windows clients silently” on page 95.</p>

An NTFS disk partition is required for all installation types.

The NetBackup client version that you install must be the same or earlier than the installed version of NetBackup server software. Later client versions cannot be used with earlier server versions.

See [“About compatibility between NetBackup versions”](#) on page 11.

See [“About NetBackup client installation”](#) on page 85.

See [“About the NetBackup preinstallation Environment Checker”](#) on page 56.

Installing NetBackup Windows clients locally or remotely

Use this procedure to install NetBackup on your local computer or on multiple computers on your network. You can stop the installation process at any time by clicking **Cancel** or by clicking **Back** to return to the previous window.

When you install Windows clients remotely, note the following:

Requirements	Review the requirements for Windows client installation. See “About Windows client installation methods and requirements” on page 86.
Privileges	You must have administrator privileges on the remote clients for the NetBackup installation to complete successfully.
Client name entries	During installation, the client name is written to the registry in lowercase. For backups to work, the policies on the NetBackup server must specify the client names in lowercase.

Note: After client installation, you may need to restart the system for the changes to take effect. A message appears to alert you if a restart is necessary

To install NetBackup client software locally or remotely on Windows systems

- 1 Log on as administrator on the host where you want to install the client software.
- 2 Start the NetBackup Installation Wizard with one of the following methods:
 - DVD media
Insert the NetBackup for Windows DVD in the drive. If Autorun is disabled, navigate to the DVD drive and run `Browser.exe`.
 - ESD images (downloaded files)
Navigate to the directory where the images reside and run `Browser.exe`.
- 3 On the initial screen, select **Installation**.
- 4 On the **Installation** screen, select **Client Software Installation**.
- 5 On the **Welcome** screen, review the content and click **Next**.
- 6 (Conditional) If you previously installed NetBackup 7.7.1 on this host, you see the **Program Maintenance** dialog.

- Select **Modify** to change installation settings for the local host, or to use the local host as a platform to perform push installation to remote hosts.
 - Select **Repair** to restore NetBackup 7.7.1 to its original state on the local host.
 - Select **Remove** to remove NetBackup 7.7.1 from the local host.
- 7 On the **License Agreement** screen, accept the terms of the agreement and click **Next**.
- 8 On the **Symantec NetBackup Client Installation Type** screen, provide the following information:

Where to install

For a local installation, select **Install to this computer only**.

For remote installation, select **Install to multiple computers on your network**.

The procedure does not install the client on the local host unless you add it to the list of systems that you want to install.

Typical

Select this option to install NetBackup with the default settings.

Custom

Select this option to install NetBackup with the settings that you want.

Click **Next**.

- 9 (Conditional) This step applies only to local **Custom** installations.
- On the **Symantec NetBackup Client Destination Folder** screen, you can select where the NetBackup files are installed.

Destination Folder

By default, NetBackup files are installed to the following location:

C:\Program Files\VERITAS

To change the folder destination where NetBackup is installed:

- Click **Change**.
- Browse to the preferred location and designate a new or an existing folder.
- Click **Next**.

Additional information about installation folder restrictions is available.

See ["Restrictions on the NetBackup installation directory"](#) on page 10.

Note: For upgrades, you cannot change the destination.

10 (Conditional) This step applies only to **Custom** installations.

On the **NetBackup Options** screen, select from the following options:

At System Startup

Enable or disable the following options:

- **Start NetBackup Client Service Automatically**
By default, this option is enabled so that NetBackup services are available immediately after system startup.
- **Start NetBackup Client Job Tracker Automatically**
By default, this option is disabled. To start this option manually after installation, click **Start > All Programs > Symantec NetBackup > NetBackup Client Job Tracker**.

Ports

On this screen, you can change port numbers, if it is necessary in your configuration.

You may need to change a port number if you encounter conflicts when NetBackup and another industry product try to share the same port. Another example is if a port conflict occurs with a firewall, which may cause security issues.

To change a port number, select the port number that you want to replace and type the new number.

Click **Next**.

- 11 On the **NetBackup Services** screen, provide the following startup account and startup type information for NetBackup client services:

Log On

Specify either **Local System account** or **This account**.

By default, the **Local System account** is selected, so that NetBackup uses the built-in system account. When this option is selected, the fields below it are disabled.

To specify a different system account:

- Select this option.
- Enter the account information in the following fields:

Domain

Username

Password

Safe Abort Option

This option determines how the installation proceeds if a restart is required as part of the installation or upgrade.

If you select this option and the installation process determines that a restart is required, the installation (or upgrade) stops. The system is then rolled back to its original state.

If you do not select this option, the installation (or upgrade) proceeds even if the installation process determines that a restart is required.

- 12 On the **NetBackup System Names** screen, the following fields are populated automatically. Changes are not normally required. Except for the **Client Name**, you can make changes as needed for your configuration.

Client Name

Do not change this name.

Master Server Name

If necessary, change this name to the appropriate master server where the client backup images are to be stored.

Additional Servers

Enter all of the master server and media server names that you want this client to access.

- 13 On the **Symantec NetBackup Remote Hosts** screen, specify the hosts where you want NetBackup installed.

- **Destination Systems**

Right-click the **Windows Destination Computers** icon and select from the drop-down menu , or use the following icons:

Browse

Click here to search the network for the hosts where you want to install NetBackup.

- On the **Available Systems** dialog box, select the computer to add and click **Next**.
- On the **Remote Computer Login Credentials** dialog box, enter the **User Name** and the **Password** of the account to be used to perform the installation on the remote computers.
- If you plan to install to multiple remote computers, click the box next to **Remember User Name and Password**. Selecting this option prevents the need to enter this information for each remote computer.
- Click **OK**.
- On the **Remote Destination Folder** dialog box, verify or change the **Destination Folder** where NetBackup is installed.

The default location is `C:\Program Files\Veritas.`

If you plan to install to multiple remote computers and you want to use the same location, click the box next to **Use this folder for subsequent systems**. Selecting this option prevents the need to enter the location for each remote computer.

Import

Click here to import a text file that contains a list of host names. When you create the text file, the host names must be defined in the following format:

`Domain\ComputerName`

Add

Click here to add a host manually.

- On the **Manual Remote Computer Selection** dialog box appears, enter the **Domain** and the **Computer Name**, then click **OK**.
- On the **Remote Computer Login Credentials** dialog box, enter the **User Name** and the **Password** of the account to be used to perform the installation on the remote computers.
If you plan to add and install to multiple remote computers, click the box next to **Remember User Name and Password**. Selecting this option prevents the need to enter this information for each remote computer.
- Click **OK**.
- On the **Remote Destination Folder** dialog box, verify or change the **Destination Folder** where NetBackup is installed.
The default location is `C:\Program Files\Veritas`.
If you plan to install to multiple remote computers and you want to use the same location, click the box next to **Use this folder for subsequent systems**. Selecting this option prevents the need to enter the location for each remote computer.
- Click **OK**.

Remove

To remove a host from the **Destination Systems** list, select the host and click here.

Change

Click here to change the destination for NetBackup file installation on the selected remote host.

- Click **Next**.

- 14 On the **Ready to Install the Program** screen, review the **Installation Summary** that shows your selections from the previous steps.

Note: Symantec recommends that you review the summary screen for any warning messages. You can prevent installation and upgrade issues if you resolve any problems before you continue the installation.

Then select one of the following options:

- Click **Install** to start the installation.

- Click **Back** to view the previous screens and make any changes, then return to this screen and click **Install**.
- Click **Cancel** to cancel the installation.

After you click **Install**, the installation process begins and a screen appears that shows you the installation progress. This process may take several minutes.

Up to five remote installations occur simultaneously. When a remote installation is completed, another one begins so that a maximum of five installations are in progress.

If you click **Cancel** after you click **Install**, the installation does not stop immediately. Installation continues on all remote hosts where the installation has already started. Any specified hosts after that point do not get client software installed.

NetBackup considers any remote installations that were completed when you clicked **Cancel** to be successful.

15 On the **Installation Complete** screen, click **Finish**.

Examine the installation log on the following location:

```
%ALLUSERSPROFILE%\Symantec\NetBackup\InstallLogs\
```

An installation log file provides detailed installation information and shows whether any errors occurred.

Note: When you perform a remote installation to multiple computers, this option only lets you view the log for the local computer. Each computer that you selected for installation contains its own installation log file. To view the log file of a remote computer, open a Windows Explorer window, enter `\\<COMPUTERNAME>`, and navigate to the `InstallLogs` directory.

Search the installation log for the following error indications:

- Strings that include `Return Value 3`.
- Starting with NetBackup 7.0, important log messages are color coded as follows:
 - Yellow = warning.
 - Red = error.

Installing NetBackup Windows clients silently

A silent installation process does not require interactive input. It does, however, require that you edit the `silentclient.cmd` file before you run it.

Silent installations of NetBackup clients are not supported if you want to run the NetBackup services as a user instead of a local administrator.

To install NetBackup with a custom services account, refer to the following topics:

See [“Installing NetBackup Windows clients locally or remotely”](#) on page 89.

Use the following procedure to perform a silent installation of a local NetBackup client.

To perform a silent installation of NetBackup client software on Windows

- 1 Insert the NetBackup installation DVD in the drive or navigate to the location where the ESD images (downloaded files) reside.
- 2 In a **Microsoft Windows Explorer** window, navigate to the DVD drive.
- 3 Copy the contents of the one of the following directories to a temporary folder on your hard drive. For example, C:\temp.
 - PC_ClnT\x86
 - PC_ClnT\x64
- 4 Since the original source files are read-only, change the permissions for the copied files on the hard drive to allow the update.
- 5 In the temporary directory, use a text editor to edit the `silentclient.cmd` file so the script installs the client software as needed.
- 6 Run the `silentclient.cmd` script.
- 7 To verify that the installation was successful, check the installation log file in the following directory:

```
%ALLUSERSPROFILE%\Symantec\NetBackup\InstallLogs
```

How to configure NetBackup clients

You can configure NetBackup clients by performing one of the following actions:

- | | |
|--|---|
| To add servers or media servers: | <ul style="list-style-type: none">■ Start the Backup, Archive, and Restore interface.■ Click File > Specify NetBackup Machines. |
| To display and change the client properties: | <ul style="list-style-type: none">■ Start the Backup, Archive, and Restore interface.■ Click File > NetBackup Client Properties. |

To display and change the server properties:

- Open the NetBackup Administration Console.
- Expand **Host Properties** and click **Clients**.
- In the right pane, right-click on the client and choose **Properties**.

In the dialog box that appears, on the **Servers** tab, all NetBackup servers that require access to your Windows client must be listed.

For complete information on client configuration, see the *NetBackup Administrator's Guide, Volume I*.

<http://www.symantec.com/docs/DOC5332>

About NetBackup client installation on UNIX/Linux

You can install UNIX/Linux clients either locally at the client computer or remotely from your UNIX/Linux NetBackup server. To install client software remotely from a UNIX/Linux NetBackup server, the client type software must first be installed on the UNIX/Linux server.

Note: Macintosh OS X clients are UNIX-based clients. Follow the installation procedures in this section.

Note the following when you install NetBackup client software on UNIX/Linux systems:

UNIX/Linux package consolidation

Starting with NetBackup 7.0, many of the add-on products and database agents are now installed with the NetBackup client package. Separate installation for these products is no longer needed.

The following products are now included in the NetBackup 7.7.1 client package (if the platform supports the product):

- BMR Boot server
- DB2
- Encryption
- Informix
- LiveUpdate agent
- Lotus Notes
- Oracle
- SAP
- Snapshot Client
- Sybase

The binaries for the listed products are laid down with the client package. A valid license is still required to enable the product. If product configuration was required previously (such as `db2_config`), configuration is still required.

The French, Japanese, and Chinese language packages remain as separate add-ons. The process to install and upgrade these products remains the same.

`gzip` and `gunzip` commands

The `gzip` and the `gunzip` commands must be installed on each system. The directories where the commands are installed must be part of the root user's `PATH` environment variable setting.

NetBackup-Java compatibility To initiate a backup or a restore from a UNIX/Linux client, the following graphical interfaces are available:

- Clients that are compatible with NetBackup-Java may use the NetBackup-Java interface (jbpSA).
- Clients that are not compatible with NetBackup-Java can use the bp interface. They also support a login from any NetBackup 7.7 UNIX server's NetBackup client console with the jbpSA command.

More information about compatibility with graphical interfaces is available. Refer to the NetBackup Software Compatibility List (SCL).

<http://www.netbackup.com/compatibility>

Note: If a client is listed in the *Client Selections for Backup Policies* section of the SCL but not in the *NetBackup Administration Consoles* section, the client is supported for backup and restore, but it does not support any of the available graphical interfaces.

About UNIX/Linux client installation methods

You can install NetBackup clients on UNIX/Linux systems with the following methods:

Local installations

- This method installs the client software on the computer where you run the installation script.
- To install clients to a location other than the default, you must create and link a directory before you install the client software. First create the directory where you want the software to reside, then create `/usr/openv` as a link to that directory.
- On IBM zSeries Linux clients, you must transfer the NetBackup DVD or ESD image contents to a location that is readable by the virtual Linux environment. You can transfer the image with FTP or NFS mounting commands.

See “Installing UNIX clients locally” on page 100.

- Remote (push) installations
- You can "push" the client software from your UNIX/Linux NetBackup server to your UNIX/Linux client computers. The UNIX/Linux client must be a true client and not a media server or a master server. The preferred installation method is to push the client software.
 - Before you can push to a UNIX/Linux client, you must first install the NetBackup client type software on the server. Then, you must create a policy that includes the client name.
<http://www.symantec.com/docs/DOC5332>
See "Installing client type software on a master server" on page 50.
 - You cannot install Windows client software remotely from a NetBackup UNIX/Linux server.
 - Firewalls can prevent remote client installation.
 - Clients such as the IBM zSeries Linux may not have a locally mounted DVD device or access to the NetBackup DVD or ESD images. In these cases, you must push the client software from a UNIX/Linux master server or a media server.
 - The following remote installation methods are available:
See "Installing client software with the ftp method" on page 104.
See "Installing client software with the rsh method" on page 103.
See "Installing client software with the ssh method" on page 106.
See "Installing client software with the sftp method" on page 107.

See "About NetBackup client installation" on page 85.

Installing UNIX clients locally

The following procedure installs the NetBackup client software on a local computer.

To install client software locally on a UNIX client

- 1 Use one of the following methods to start the installation script:

DVD

- Insert the NetBackup UNIX Clients DVD into the drive.
See [“About the NetBackup media kit”](#) on page 18.
- If necessary, mount the DVD.
See [“About mounting the NetBackup software media”](#) on page 37.
- Enter the following command:

```
dvd_directory/install
```

The *dvd_directory* is the path to the directory where you can access the DVD.

- ESD images (downloaded files)
- Navigate to the location where the installation images reside.
- Enter the following command:

```
./install
```

2 When the following message appears, press **Enter** to continue:

```
Symantec Installation Script  
Copyright 1993 - 2013 Symantec Corporation, All Rights Reserved.
```

```
Installing NetBackup Client Software
```

```
Please review the SYMANTEC SOFTWARE LICENSE AGREEMENT located on  
the installation media before proceeding. The agreement includes  
details on the NetBackup Product Improvement Program.
```

```
For NetBackup installation and upgrade information specific to your  
platform and to find out if your installed EEBs or hot fixes are  
contained in this release, check out the Symantec Operations Readiness  
Tools (SORT) Installation and Upgrade Checklist and Hot fix and EEB  
Release Auditor, respectively, at https://sort.symantec.com/netbackup.
```

```
Do you wish to continue? [y,n] (y)
```

The client binaries represent the operating system versions where the binaries were compiled. The binaries typically function perfectly on later versions of the operating system. The installation procedure attempts to load the appropriate binaries for your system. If the script does not recognize the local operating system, it presents choices.

3 Follow the prompts to complete the installation.

Additional information about installation folder restrictions is available.

See [“Restrictions on the NetBackup installation directory”](#) on page 10.

4 After the installation is complete, select **Exit from this Script**.

About remote installation methods for UNIX/Linux clients

You can push the client software from a UNIX/Linux master server to a client host by using the following methods:

- `rsh`
See [“Installing client software with the rsh method”](#) on page 103.
- `ftp`
See [“Installing client software with the ftp method”](#) on page 104.
- `ssh`
See [“Installing client software with the ssh method”](#) on page 106.
- `sftp`
See [“Installing client software with the sftp method”](#) on page 107.

Note: For installation in clustered environments, enter the virtual name for the NetBackup server and not the actual local host name. You can only push client software from the active node.

Installing client software with the rsh method

Before you perform this procedure, read the following guidelines:

Client <code>.rhosts</code> file	To use this method, the UNIX client must have an entry for the server in its <code>.rhosts</code> file. The <code>.rhosts</code> entries enable software installation, but they are not necessary for correct operation of NetBackup software.
Client software location	<p>If you want to install client software to a location other than the default, you must first create and link to the desired directory. Create the directory where you want the client software to reside, and then create <code>/usr/openv</code> as a link to that directory.</p> <p>Additional information about installation folder restrictions is available.</p> <p>See “Restrictions on the NetBackup installation directory” on page 10.</p>
Backup policies	Make sure that the clients are assigned to a backup policy.
For Macintosh OS X	<p>By default, this operating system version does not enable the Remote Shell daemon (<code>rshd</code>). Run the following command to enable the daemon:</p> <pre>launchctl load -w /System/Library/LaunchDaemons/shell.plist</pre>

To install client software from a UNIX master server to UNIX clients with the `rsh` method

- 1 Start the **NetBackup Administration Console**.
- 2 On the **Login** dialog box, provide the name of the NetBackup server that contains the policy configuration with the clients.

You can install the client software only from the NetBackup server that you specify in the **Login** dialog box when you start the interface. The clients must be defined in a policy on this NetBackup server.
- 3 In the main **NetBackup Administration Console** window, do the following:
 - In the left pane where the master server properties appear, click the icon next to **NetBackup Management**. The tree expands to show the available options.
 - In the center **All Policies** pane, select the master server.
- 4 Click **Actions > Install UNIX Client Software**. This action opens the **Install UNIX Client Software** window.
- 5 Select the client names to install from the **Don't install these clients** list and click **Add >>**.

The clients are moved to the **Install these clients** list.
- 6 To start the installation, click **Install Client Software**.

You cannot stop the installation after it has started.

Client software installation can take a minute or more per client. NetBackup writes messages in the **Progress** field as the installation proceeds.

During installation, NetBackup copies client software from `/usr/opensv/netbackup/client` on the server to `/usr/opensv` on the client.

If the installation fails on a client, NetBackup notifies you but keeps the client in the policy.
- 7 After the installation is complete, click **Close**.

Installing client software with the ftp method

Before you perform this procedure, read the following guidelines:

Access to clients

You must have a login ID and password that you can use to access the clients through FTP.

Client software location	<p>If you want to install client software to a location other than the default, you must first create and link the desired directory. Create the directory where you want the software to reside, and then create <code>/usr/opensv</code> as a link to that directory.</p> <p>Additional information about installation folder restrictions is available.</p> <p>See “Restrictions on the NetBackup installation directory” on page 10.</p>
Backup policies	Make sure that the clients are assigned to a backup policy.
Macintosh OS X	<p>By default, this operating system version does not enable the FTP daemon (<code>ftpd</code>), which is required. To enable the daemon, run the following command:</p> <pre>launchctl load -w /System/Library/LaunchDaemons/ftp.plist</pre>

To install client software from a UNIX master server to UNIX clients with the ftp method

- 1 To move the client software from the server to the `/tmp` directory on the client, run the `install_client_files` script on the NetBackup server.

Use one of the following commands:

- To move software to one client at a time, enter the following command:

```
/usr/opensv/netbackup/bin/install_client_files ftp client user
```

The `client` is the host name of the client.
The `user` is the login ID that FTP requires on the client.
- To move software to all clients at once:

```
/usr/opensv/netbackup/bin/install_client_files ftp ALL user
```

The `ALL` option specifies that you want to install all clients that are configured in any backup policy on the server.
The `user` is the login ID required by FTP on the client.
If you have not set up a `.netrc` file, the `install_client_files` script prompts you for a password for each client.

- 2 After the script runs, the root user on each client computer must run the following script:

```
sh /tmp/bp.<pid>/client_config
```

The `pid` is the process ID. The `client_config` script installs the binaries.

Installing client software with the ssh method

This client installation method is based on the usage of the SunSSH and the OpenSSH products, which must be at specific version and patch levels. For more information about these patches, please refer to the *Symantec NetBackup 7.7.1 Release Notes*.

Before you perform this procedure, read the following guidelines:

SSH daemon (<code>sshd</code>)	To use the ssh method, the UNIX client must have <code>sshd</code> enabled and configured to allow root user logins.
Client software location	<p>If you want to install client software to a location other than the default, you must first create and link the desired directory. Create the directory where you want the client software to reside, and then create <code>/usr/openv</code> as a link to that directory.</p> <p>Additional information about installation folder restrictions is available.</p> <p>See "Restrictions on the NetBackup installation directory" on page 10.</p>
Backup policies	Make sure that the clients are assigned to a backup policy.
Macintosh OS X	<p>By default, this operating system version does not enable <code>sshd</code>. You must first enable this daemon to perform the following procedure successfully.</p> <ul style="list-style-type: none">■ In the System Preferences pane, select Sharing.■ Select Remote Login to enable <code>sshd</code>.

To install client software from a UNIX master server to UNIX clients with the ssh method

- ◆ On the NetBackup server, run the `install_client_files` script.

Use one of the following commands:

- To move software to only one client at a time:

```
/usr/openv/netbackup/bin/install_client_files ssh client
```

The `client` is the host name of the client.

- To move software to all clients at once:

```
/usr/openv/netbackup/bin/install_client_files ssh ALL
```

The `ALL` option specifies that you want to install all clients that are configured in any backup policy on the server.

Installing client software with the sftp method

This client installation method is based on the usage of the SunSSH and the OpenSSH products, which must be at specific version and patch levels. For more information about these patches, please refer to the *Symantec NetBackup 7.7.1 Release Notes*.

Before you perform this procedure, read the following guidelines:

SSH daemon (<code>sshd</code>)	To use this method, the UNIX client must have <code>sshd</code> enabled and configured to allow root or non-root user logins.
Client file location	<p>If you want to install client software to a location other than the default, you must first create and link the desired directory. Create the directory where you want the software to reside, and then create <code>/usr/opensv</code> as a link to that directory.</p> <p>Additional information about installation folder restrictions is available.</p> <p>See “Restrictions on the NetBackup installation directory” on page 10.</p>
Backup policies	Make sure that the clients are assigned to a backup policy.
Macintosh OS X	<p>By default, these operating system versions do not enable <code>ssh</code>. You must first enable this daemon to perform the following procedure successfully.</p> <ul style="list-style-type: none">■ In the System Preferences pane, select Sharing.■ Select Remote Login to enable <code>sshd</code>.

To install client software from a UNIX master server to UNIX clients with the sftp method

- 1 To move the client software from the server to the `/tmp` directory on the client, run the `install_client_files` script on the NetBackup server.

Use one of the following commands:

- To move software to one client at a time:

```
/usr/opensv/netbackup/bin/install_client_files sftp client user
```

The *client* is the host name of the client.
The *user* is the login ID that SSH requires on the client.
- To move software to all clients at once:

```
/usr/opensv/netbackup/bin/install_client_files sftp ALL user
```

The *ALL* option specifies that you want to install all clients that are configured in any backup policy on the server.

The *user* is the login ID required by FTP on the client.

- 2 After the script runs, the root user on each client computer must run the following script:

```
sh /tmp/bp.<pid>/client_config
```

The *pid* is the process ID. The *client_config* script installs the binaries.

Adding a UNIX/Linux client after initial server installation

You may want to add UNIX/Linux clients after the server installation if you forgot to select one during the installation. You may also add a new UNIX/Linux client type to your backup environment.

To install client software later, you must first install the NetBackup client software onto the NetBackup server.

To add UNIX/Linux client types to servers after initial installation

- 1 Use one of the following methods to start the installation script:

DVD

- Insert the NetBackup UNIX Clients DVD into the drive.
See [“About the NetBackup media kit”](#) on page 18.
- If necessary, mount the DVD.
See [“About mounting the NetBackup software media”](#) on page 37.
- Enter the following command:

```
dvd_directory/install
```

The *dvd_directory* is the path to the directory where you can access the DVD.

- ESD images (downloaded files)
- Navigate to the location where the installation images reside.
- Enter the following command:

```
./install
```

2 When the following message appears, press **Enter** to continue:

```
Symantec Installation Script  
Copyright 1993 - 2013 Symantec Corporation, All Rights Reserved.
```

```
Installing NetBackup Client Software
```

```
Please review the SYMANTEC SOFTWARE LICENSE AGREEMENT located on  
the installation media before proceeding. The agreement includes  
details on the NetBackup Product Improvement Program.
```

```
For NetBackup installation and upgrade information specific to your  
platform and to find out if your installed EEBs or hot fixes are  
contained in this release, check out the Symantec Operations Readiness  
Tools (SORT) Installation and Upgrade Checklist and Hot fix and EEB  
Release Auditor, respectively, at https://sort.symantec.com/netbackup.
```

```
Do you wish to continue? [y,n] (y)
```

The client binaries represent the operating system versions where the binaries were compiled. The binaries typically function perfectly on later versions of the operating system. The installation procedure attempts to load the appropriate binaries for your system. If the script does not recognize the local operating system, it presents choices.

3 Select the client type that you want to load and follow the prompts to install that client type. Repeat as necessary until all of the client types you want are loaded.

Make sure that you load the software for all of the UNIX/Linux client types that you intend to install remotely from the server.

4 After the installation is complete, unmount the DVD.

5 Install the NetBackup client software on the clients you specified.

See [“About remote installation methods for UNIX/Linux clients”](#) on page 102.

Upgrading clients after servers are upgraded

The `update_clients` installation script lets you push client software to clients. It does not let you push client software to a remote client that is also a NetBackup media or master server. You cannot push software this way because the server software and client binaries must be of the same version on a single host.

The `update_clients` installation script can determine the full client list that is configured on the server. When it is run without any parameters, it attempts to update all clients (as determined by `/usr/opensv/netbackup/bin/admincmd/bpplclients`). If you do not want to upgrade all clients, you can specify a subset of clients. Use the hardware type and operating system parameters or use the `-ClientList` parameter.

You can run `update_clients` from a media server. The `-ClientList` parameter is required in this situation. The script lets you maintain a media server and a set of clients at an earlier release level than the master server. Doing so requires the informed use of the `update_clients -ClientList` command on a master server and a media server to avoid unwanted client upgrades.

For clustered environments, you can push client software only from the active node.

During a client upgrade, the new client files are written to a directory in `/tmp` on the client. This directory must have sufficient space to temporarily store the new client files to ensure a successful upgrade. If sufficient space is not available, a status message informs you that the upgrade script could not write to the location in the `/tmp` directory. To resolve this issue, allocate more space to the `/tmp` directory and perform the upgrade procedure again. The temporary directory is removed when the upgrade is complete.

To upgrade clients after you have upgraded servers

1 Use one of the following methods to start the installation script:

DVD

- Insert the NetBackup UNIX Clients DVD into the drive.
See [“About the NetBackup media kit”](#) on page 18.
- If necessary, mount the DVD.
See [“Mounting NetBackup software media on UNIX or Linux systems”](#) on page 38.
- Enter the following command:

```
cd_directory/install
```

The `cd_directory` is the path to the directory where you can access the DVD.

- ESD images (downloaded files)
- Navigate to the location where the installation images reside.
 - Enter the following command:

```
./install
```

2 When the following message appears, press **Enter** to continue:

```
Installing NetBackup Client Software.  
Do you wish to continue? (y/n) [y]
```

The client binaries represent the operating system versions where the binaries were compiled. The binaries typically function perfectly on later versions of the operating system. For example, HP PA-RISC 11.11 binaries also are used on the HP PA-RISC 11.23 level of the operating system.

3 Select the client type that you want to load and follow the prompts to load that client type. Repeat as necessary until all desired client types have been loaded.

Make sure that you load the software for all of the UNIX client types that you intend to push to from this server. Otherwise, you cannot add these client types to the NetBackup policy configuration.

4 After the installation is complete, unmount the DVD.

5 As a root user on the NetBackup master server, enter the following command to see whether `bprcd` is running:

```
/usr/opensv/netbackup/bin/bpps
```

If `bprcd` is running, stop it with the following command:

```
/usr/opensv/netbackup/bin/admincmd/bprdreq -terminate
```

6 Enter the following command to make sure that backups or restores are not in progress:

```
/usr/opensv/netbackup/bin/admincmd/bpobjobs
```

7 Update UNIX client software by running the `update_clients` script. Specify the host names of the individual nodes (not virtual names) in the list of clients.

Use one of the following commands:

If you do not use a `-ClientList` file: `/usr/opensv/netbackup/bin/update_clients`

If you use a `-ClientList` file: `/usr/opensv/netbackup/bin/update_clients -ClientList filename`

The `-ClientList` parameter is required on a media server.

For more than 30 clients, you can divide the list into multiple files and run `update_clients` for each file.

To create a client list file, perform the following steps:

- Change to the NetBackup `admincmd` directory, as follows:

```
cd /usr/opensv/netbackup/bin/admincmd
```

- Use the `bpplclients` command to create a file that contains a list of clients currently configured in the NetBackup database. The options to use on this command differ depending on whether you push from a master server or from a media server, as follows:

If you push from the master server: `./bpplclients -allunique -noheader > file`

If you push from a media server: `./bpplclients -allunique -noheader -M \m_server_name > file`

The option descriptions are as follows:

`m_server_name` Name of the NetBackup master server in this environment.

`file` Name of the file to contain the list of unique clients. If no clients have been configured in the NetBackup database, the file is empty.

The `bpplclients` command writes output to `file` in the following format:

```
hardware os client
```

`hardware` The hardware name. For example, run the `ls` command in directory `/usr/opensv/netbackup/client`.

`os` The operating system name. For example, run the `ls` command in directory `/usr/opensv/netbackup/client/hardware`.

`client` The name of the client.

The contents of `file` might look like the following example:

```
Solaris Solaris9 curry
```

- (Optional) Edit `file`.
Perform this step to change the contents of `file`. Edit `file` to contain only those clients you want to update with NetBackup client software. The host names of the clients must be the clients' individual node names. They cannot be virtual names. The `hostname` command and the `domainname` command return the correct values for the individual node names. The format can be either `hostname` or `hostname.domainname`.

- 8 The `update_clients` script requests information from you. The following information appears in the script:

```
Starting update_clients script.  
There are N clients to upgrade.  
Do you want the bp.conf file on the clients updated to list this  
server as the master server? (y/n) [y]
```

Type either **y** or **n**.

```
Enter the number of simultaneous updates you wish to take  
place. [1 - 30] (default: 15):
```

Press **Enter**.

```
The upgrade will likely take Y to Z minutes.  
Do you want to upgrade clients now? (y/n) [y]
```

Type either **y** or **n**.

- 9 After all servers and clients are updated, start the `bprd` daemon as the root user on the master server by entering the following command:

```
/usr/opensv/netbackup/bin/initbprd
```

Configuring NetBackup

This chapter includes the following topics:

- [About NetBackup startup and shutdown scripts](#)
- [About NetBackup server configuration](#)

About NetBackup startup and shutdown scripts

When you install NetBackup, the installation script also performs configuration of startup and shutdown scripts. Startup scripts allow the NetBackup daemons to start automatically when the system boots. Shutdown scripts automatically terminate the startup scripts at system shutdown.

The installation process copies the NetBackup startup and shutdown scripts to the appropriate operating system location.

For non-cluster upgrades, any existing NetBackup related startup and shutdown scripts are saved, and the newly released versions of those scripts are installed.

[Table 7-1](#) lists the links for the startup and the shutdown scripts for the various platforms that are installed during NetBackup installation.

Table 7-1 NetBackup startup and shutdown script links by platform

Platform	Links
AIX	<pre>/etc/rc.netbackup.aix</pre> <ul style="list-style-type: none"> ■ The NetBackup installation script edited the <code>/etc/inittab</code> file and added the following entry to ensure that the script is called during a level-two boot: <pre>netbackup:2:wait:/etc/rc.netbackup.aix</pre> ■ To shut down, add the following line to the <code>/etc/rc.shutdown</code> file: <pre>/etc/rc.netbackup.aix stop</pre>
FreeBSD	<pre>/usr/local/etc/rc.d/S77netbackup.sh ->/usr/local/etc/netbackup</pre>
HP-UX	<pre>/sbin/rc1.d/K001netbackup ->/sbin/init.d/netbackup /sbin/rc2.d/S777netbackup ->/sbin/init.d/netbackup</pre>
Linux Debian	<pre>/etc/rc0.d/K01netbackup ->/etc/init.d/netbackup /etc/rc1.d/K01netbackup ->/etc/init.d/netbackup /etc/rc2.d/S95netbackup ->/etc/init.d/netbackup</pre>
Linux Red Hat	<pre>/etc/rc.d/rc0.d/K01netbackup ->/etc/rc.d/init.d/netbackup /etc/rc.d/rc1.d/K01netbackup ->/etc/rc.d/init.d/netbackup /etc/rc.d/rc2.d/S77netbackup ->/etc/rc.d/init.d/netbackup /etc/rc.d/rc3.d/S77netbackup ->/etc/rc.d/init.d/netbackup /etc/rc.d/rc5.d/S77netbackup ->/etc/rc.d/init.d/netbackup /etc/rc.d/rc6.d/K01netbackup ->/etc/rc.d/init.d/netbackup</pre>

Table 7-1 NetBackup startup and shutdown script links by platform (*continued*)

Platform	Links
Linux SUSE	/etc/init.d/rc0.d/K01netbackup ->/etc/init.d/netbackup /etc/init.d/rc2.d/S77netbackup ->/etc/init.d/netbackup /etc/init.d/rc3.d/S77netbackup ->/etc/init.d/netbackup /etc/init.d/rc5.d/S77netbackup ->/etc/init.d/netbackup /etc/init.d/rc6.d/K01netbackup ->/etc/init.d/netbackup
Macintosh OSX	/Library/StartupItems/netbackup/Resources/netbackup /Library/StartupItems/netbackup/StartupParameters.plist /Library/StartupItems/netbackup/netbackup
Solaris	/etc/rc0.d/K01netbackup ->/etc/init.d/netbackup /etc/rc1.d/K01netbackup ->/etc/init.d/netbackup /etc/rc2.d/S77netbackup ->/etc/init.d/netbackup

About NetBackup server configuration

After all server software is installed, you are ready to configure NetBackup to work with the robotic and the storage devices in your environment. Remember the operating system must recognize these devices as configured before you can configure them in NetBackup.

See [“About storage device configuration”](#) on page 20.

Use the following guidelines when you configure NetBackup:

NetBackup Enterprise servers The procedures for configuring master and media servers are very similar. Symantec recommends, however, that you configure all server information such as storage devices and volumes from the master server. Following this order helps ensure that the master servers properly administer the media servers.

Warning: Communication problems between the master server and the media server do not prevent you from running the configuration wizards. Therefore, do not run the wizards on the media server until the problems are corrected. If you run any of the wizards when a communication problem exists, the master server cannot recognize the information that you enter. You must first correct the problem. After you correct the problem, run the configuration wizards from the master server.

Clustered environments

- Configure devices on every node in the cluster.
- Start by configuring all storage devices from the active node so that they work with NetBackup.
- For a NetBackup failover server, attach all of the devices to each node in the cluster on which NetBackup is installed. Refer to the clustering vendor's documentation for information on how to migrate to another node.
- Unless otherwise noted, configure NetBackup to use the virtual host names of master servers and media servers in the cluster.

For complete information on to how to configure an add-on product to fail over, see the *NetBackup Clustered Master Server Administrator's Guide*.

<http://www.symantec.com/docs/DOC5332>

For initial NetBackup server configuration, Symantec recommends that you launch the NetBackup Administration Console and click the **Getting Started** icon. A series of wizards guide you through the following configuration procedures:

- **Configure Storage Devices**
See "[About the Device Configuration Wizard](#)" on page 119.
- **Configure Volumes**
See "[About the Volume Configuration Wizard](#)" on page 121.
- **Configure the Catalog Backup**
See "[About the Catalog Backup Wizard](#)" on page 122.
- **Create a Backup Policy**
See "[About the Backup Policy Configuration Wizard](#)" on page 123.

If NetBackup is already configured and you want to change a specific area, click the appropriate wizard on the NetBackup Administration Console.

For complete information on all of the NetBackup wizards and how to configure NetBackup, see the *NetBackup Administrator's Guide, Volume I*.

<http://www.symantec.com/docs/DOC5332>

See “[About storage device configuration](#)” on page 20.

Starting the NetBackup Administration Console

Use the following procedures to open the NetBackup Administration Console to configure NetBackup. The **Getting Started** wizard guides you through the primary configuration steps to make NetBackup function.

Note: Other wizards are available from the initial NetBackup Administration Console window that are not part of the **Getting Started** wizard. For example, you can configure disk pools or create a snapshot backup policy. See the *NetBackup Administrator's Guide, Volume I* for complete information about all NetBackup wizards.

<http://www.symantec.com/docs/DOC5332>

On Windows systems, if you clicked the check box **Launch Administration Console** that appears at the end of NetBackup installation, you can skip this procedure.

To start the NetBackup Administration Console on Windows

- 1 Log on to the NetBackup server as the Administrator.
- 2 Click **Start > Programs > Symantec NetBackup > NetBackup Administration Console**.
- 3 To begin configuration, on the Administration Console, click **Getting Started**.

The **Getting Started** screen appears and prompts you to begin device configuration.

Note: If you still need to configure devices to work with the operating system, close the wizard. You must first configure those devices as specified by the device and the operating system vendors.

To start the NetBackup Administration Console on UNIX

- 1 Log in to the NetBackup server as root.
For clustered environments, log in to the active node as root.
If you need to run the user interface on a computer other than the NetBackup server, log on to that computer. For UNIX systems, log in as root.
- 2 Enter the following command:

```
/usr/opensv/netbackup/bin/jnbSA &
```
- 3 Enter the password for root.
For clustered environments, when you log in to the NetBackup Administration Console, specify the virtual host name in the **Host** field.
- 4 Click **Login**.
- 5 To begin configuration, on the Administration Console, click **Getting Started**.
- 6 On the initial **Getting Started** screen, review the content and click **Next**.
The following screen prompts you to **Configure Storage Devices**.

Note: If you still need to configure devices to work with the operating system, close the wizard. You must first configure those devices as specified by the device and the operating system vendors.

About the Device Configuration Wizard

Before you can run backups, you must define your storage devices for NetBackup. This wizard guides you through this process. You must, however, be certain that you have configured your storage devices correctly for your operating system. NetBackup cannot function reliably unless devices are installed and configured correctly.

See [“About storage device configuration”](#) on page 20.

For clustered environments, begin configuring all storage devices from the active node. For a NetBackup failover server, Symantec recommends that you attach all of the devices to every node on which NetBackup is installed.

For complete instructions, refer to the *NetBackup Clustered Master Server Administrator's Guide*.

<http://www.symantec.com/docs/DOC5332>

This wizard takes you through the following processes:

- Scans the hosts for backup devices
- Verifies the devices that were automatically detected
- Verifies and corrects the drive configuration
- Updates the device configuration

The wizard presents the following information when you configure devices:

Device configuration

- When the wizard displays the **Device Hosts** screen, you must specify the hosts on which to auto-discover and configure devices (NetBackup Enterprise servers only).
- When the wizard displays the **Backup Devices** screen, confirm that the list of devices is complete and accurate. If a known backup device does not appear in this list, take the following action:
 - Verify that the backup device is physically attached to the host.
 - Verify that all that specified device and operating system vendor installation procedures are performed successfully.
 - Verify that all drives correspond to the proper device. If you need to move a drive, select the drive and drag it to the correct location.
- For clusters, ensure that you perform storage device configuration on each node. Begin on the active node, then move the NetBackup active node to another node and perform the storage device configuration on that node. Repeat for each node of the cluster on which NetBackup runs.

Note: By default, robotic daemons and NetBackup add-on products do not cause NetBackup to failover if they fail. You can configure robotic devices and NetBackup add-on products to fail over NetBackup if the robot or the add-on product fails. The operating system must recognize the robots as configured before you can configure NetBackup to failover. For complete details about fail over configuration, refer to the *NetBackup Clustered Master Server Administrator's Guide*.

<http://www.symantec.com/docs/DOC5332>

Defining storage units

- You define storage units from the **Configure Storage Units** screen. If your system does not have a tape device, you can store data on a disk by defining disk storage units.
- When you enter a path for a storage unit, the following rules apply:
 - Use the correct path separators (forward slash (/) for UNIX and backward slash (\) for Windows).
 - Use a colon (:) to specify a drive separation on Windows platforms.
 - Use the following characters only:
 - Alphabetic characters (ASCII A-Z, a-z)
 - Numeric characters (0-9)
 - Miscellaneous characters: plus (+), minus (-), underscore (_), or period (.)

See “[About the Volume Configuration Wizard](#)” on page 121.

About the Volume Configuration Wizard

After you have configured your storage devices, the Getting Started Wizard starts the Volume Configuration Wizard. However, if you only have disk storage capability, NetBackup skips this wizard.

This wizard lets you initiate an inventory of each configured robot. NetBackup automatically updates the volume database if it finds new robotic media during the inventory. In addition, you can define new volumes for use in standalone drives.

For complete information about volumes or volume configuration for standalone drives, refer to the *NetBackup Administrator's Guide, Volume I*.

<http://www.symantec.com/docs/DOC5332>

Note: For clustered environments, configure volumes from the active node.

This wizard lets you do the following tasks:

- Select a device for volume configuration
- Perform an inventory of the robot
- Create new volumes
- Create new volume groups

The wizard presents the following information when you configure volumes and perform inventory:

- | | |
|---------------------------|--|
| Robot or device inventory | <ul style="list-style-type: none"> ■ NetBackup conducts an inventory of the robot or the device that you selected. To view the results after the inventory has completed, see the Results: field. ■ After the device inventory has completed, the wizard prompts you to identify which device slots contain cleaning media.
 If you upgraded NetBackup and have pre-existing barcode rules, the barcode reader automatically detects the designated slots for the cleaning media. If you do not designate cleaning slots, NetBackup considers all media (including cleaning media) as typical media and tries to overwrite it. ■ After the inventory has completed, you are prompted to identify which device slots contain cleaning media.
 If you identify one or more slots as cleaning media in the Identify Cleaning Media screen, you see the Robot Inventory (Cleaning Media) screen. This screen displays the results after the software updates the EMM database. If you do not designate cleaning media, NetBackup considers all media to be typical media (including cleaning media) and tries to overwrite it. |
| Standalone drives | <ul style="list-style-type: none"> ■ Specify the number of volumes for the device. ■ The wizard does not let you configure cleaning tapes for standalone drives. |
| Multiple drive types | <p>When you specify multiple drive types, the following are true:</p> <ul style="list-style-type: none"> ■ Media that is written by one robot drive may not work in any other drive. If this situation occurs, NetBackup considers the robot to have more than one type of drive. ■ If the robot has more than one type of drive, the wizard cannot inventory the robot. |

See [“About the Catalog Backup Wizard”](#) on page 122.

About the Catalog Backup Wizard

The NetBackup catalog contains information about your configuration and the locations of backed up files and directories. If a disk fails and your catalog is lost, a catalog backup makes it easy to restore your data and resume your backup schedule.

Therefore, you must configure a catalog backup policy before any data gets backed up.

This wizard lets you create a policy for an online, hot catalog backup. Online, hot catalog backups can back up the catalog while normal client backups are in progress.

A catalog backup policy lets you specify the following information:

- The destinations for the catalog backup
A backup destination can be any configured storage device. For additional disaster recovery protection, you can specify a second location for your catalog backup.

Note: Although NetBackup supports catalog backup to disk, Symantec recommends that you back up the catalog to a removable media that gets stored off-site.

- When the catalog backup occurs
- The location of the disaster recovery file that is needed to recover from the catalog backup

Use the following guidelines to configure a catalog backup:

- Configure a catalog backup policy before any other files or data are backed up.
- For clustered systems, configure the catalog backup policy from the active node.

For complete details about catalog backups, see the chapter “Protecting the NetBackup catalog” in the *NetBackup Administrator's Guide, Volume I*.

<http://www.symantec.com/docs/DOC5332>

For instructions on how to configure a catalog backup in clustered environments, see the *NetBackup Clustered Master Server Administrator's Guide*.

<http://www.symantec.com/docs/DOC5332>

About the Backup Policy Configuration Wizard

This wizard lets you define a backup policy for a group of one or more clients. For clustered environments, configure the policy from the active node.

The wizard lets you specify the following:

- Policy names and types
- Clients
- Files and directories to back up
- Backup types
- Backup rotations

- Starting times of backups

The wizard prompts you to choose the type of backup that you want a policy to perform.

[Table 7-2](#) describes the available backup types.

Table 7-2 Backup type descriptions

Backup type	Description
Full backup	Backs up all files that are specified in the file list.
Incremental backup	Backs up all the changed files that are specified in the file list.
Differential backup	Also referred to as a Differential incremental backup. Backs up the files that have changed since the last successful incremental or full backup. All files are backed up if no previous backup has been done.
Cumulative backup	Also referred to as a Cumulative incremental backup . Only the files that changed since the last full backup that was successful are backed up. All files are backed up if no previous backup has been done.
User backup	Initiated manually by a user to back up specific files.

Use the following guidelines when you create backup policies:

- The list that appears on the **Client List** screen of the Backup Policy Wizard is a list of clients that are backed up. You can add, change, or delete clients from the list.
- You can select how often you want a backup policy to run for full or incremental backups. In addition, you can select the retention period for the backups.

After you have completed the Backup Policy Wizard , you are asked if you want to perform an installation verification test. To do this test, click the **Activity Monitor** in the left pane of the NetBackup Administration Console. You can now monitor the progress of the backup job.

Upgrading NetBackup software

This chapter includes the following topics:

- [About upgrading NetBackup](#)
- [About the NetBackup 7.x Upgrade Portal](#)

About upgrading NetBackup

Starting with NetBackup 7.6, information about upgrades is no longer included in the *Symantec NetBackup Installation Guide*.

Complete upgrade information can be found in the *Symantec NetBackup Upgrade Guide* on the NetBackup Upgrade Portal. The portal can be accessed by clicking on the following link:

<http://www.symantec.com/docs/TECH74584>

See “[About Symantec Operations Readiness Tools](#)” on page 11.

See “[About the NetBackup 7.x Upgrade Portal](#)” on page 125.

About the NetBackup 7.x Upgrade Portal

The NetBackup 7.x Upgrade Portal contains the necessary information and instructions for upgrades to version 7.7.1. The following is a link to the portal:

<http://www.symantec.com/docs/TECH74584>

You must perform an upgrade to NetBackup 7.7.1 as described in the portal documentation.

To help you plan and prepare for an upgrade to NetBackup 7.7.1, the following describes the important information that can be found on the portal:

- **Catalog backup**
Before the upgrade, a catalog backup should be created to provide a backup of the catalog in case of a failed upgrade.
- **NetBackup Catalog Check (NBCC) utility for NetBackup 7.7.1.**
Before the upgrade, the catalog should be checked to make sure that it is free of any inconsistencies that may cause the upgrade to fail. If the NBCC results show any catalog inconsistencies, you must seek assistance from Symantec Enterprise Support for additional guidance.
- **Upgrade to NetBackup OpsCenter 7.7.1**
The *Symantec NetBackup OpsCenter Administrator's Guide* provides important notes for upgrading to NetBackup OpsCenter 7.7.1. This upgrade must be done before you upgrade to NetBackup 7.7.1.
<http://www.symantec.com/docs/DOC5332>
- **Catalog cleanup.**
Your current NetBackup catalog must be free of any inconsistencies that may prevent a successful upgrade.
- **Upgrade to NetBackup 7.7.1**
After the catalog cleanup and the NBCC results are declared as acceptable and you have upgraded to NetBackup OpsCenter 7.7.1, begin the NetBackup 7.7.1 upgrade.

If you have any questions or concerns about the upgrade process for NetBackup 7.7.1, please contact Symantec Enterprise Support.

See “[About Symantec Operations Readiness Tools](#)” on page 11.

Removing NetBackup server software

This chapter includes the following topics:

- [About NetBackup server software removal on UNIX systems](#)
- [Removing NetBackup from UNIX servers](#)
- [About NetBackup server software removal on Windows systems](#)
- [Removing NetBackup server software on Windows systems](#)
- [Removing NetBackup server software in a clustered environment](#)
- [Removing NetBackup LiveUpdate from Windows systems](#)
- [About removal of the Java Console state data from Windows servers and Windows clients](#)

About NetBackup server software removal on UNIX systems

NetBackup removal procedures remove NetBackup completely, along with any installed add-on products. Each procedure gives you the opportunity to save any data that you want and to remove add-on products before you remove NetBackup.

Symantec recommends that you use the following order when you remove NetBackup server software:

- Save any data that you require.
This task is very important if you plan to reinstall NetBackup at a later date.
- Remove any add-on products before you remove NetBackup server software.

- Remove the NetBackup server software.

See [“Removing NetBackup from UNIX servers”](#) on page 128.

See [“About NetBackup software removal on UNIX/Linux clients”](#) on page 142.

See [“Removing NetBackup from UNIX/Linux clients”](#) on page 142.

Removing NetBackup from UNIX servers

Use this procedure to remove NetBackup from a UNIX server. You may also need to reference other documents for procedures of specific tasks to remove NetBackup successfully.

Use the following guidelines when you remove NetBackup from UNIX servers:

NetBackup relational database (NBDB) location	If you moved the NBDB files in <code>/usr/opensv/db/data</code> from their default installation location, this procedure includes a step that describes how to remove these files.
Clustered environments	<p>Before you begin to remove NetBackup, you must remove NetBackup from the cluster application. Follow the instructions in your cluster documentation on how to remove a group, then you can remove NetBackup.</p> <p>You must remove NetBackup from each node in the cluster.</p>
HP-UX Service Guard Clusters	<p>If NetBackup has been configured to run as a clustered package, you must also delete the following directory:</p> <pre><code>/etc/cmcluster/netbackup</code></pre>
PBX	<p>When you remove NetBackup, PBX is not removed. You must remove PBX manually. This procedure includes a step that describes how to perform this task.</p> <p>Warning: Do not remove PBX if your server uses other Symantec software products that require PBX to run.</p>
NetBackup Administration Console	The NetBackup Administration Console must be closed when you remove NetBackup. Otherwise, NetBackup may cause a failure that forces you to restart the procedure.

To remove NetBackup from UNIX servers

- 1 Log on as the root user on the server.
- 2 Perform a catalog backup.
- 3 If the NetBackup Administration Console is open, you must close it now.

- 4 Save all important data from any add-on products that you have installed.
- 5 Stop the NetBackup/Media Manager daemons with the following command:

```
/usr/opensv/netbackup/bin/bp.kill_all
```

- 6 Identify any installed add-on products by using the following command:

AIX	<code>lslpp -L</code>
HP-UX	<code>swlist</code>
Linux	<code>rpm -qa</code>
Solaris	<code>pkginfo</code>

Seven add-on products can be installed on the server. They are:

```
SYMCfrnb
SYMCfrnbclt
SYMCjanb
SYMCjanbclt
SYMCzbnb
SYMCzbnbclt
SYMCnbsds
```

Remove any add-on products found.

- 7 For Solaris systems only, run the following command:

```
/usr/opensv/volmgr/bin/driver/sg.install -deinstall
```

- 8 To unregister NetBackup from the VxUL master configuration that is stored in the `/etc/vx/vrtslog.conf` file, run the following command:

```
/usr/opensv/netbackup/bin/vxlogcfg -r -p 51216
```

The `-p` option specifies the product ID, which is 51216 for NetBackup.

- 9 If BMR is supported and enabled on the server, remove the associated files with the following command:

```
/usr/opensv/netbackup/bin/bmrsetupmaster -undo -f
```

- 10 To unregister all NetBackup products with LiveUpdate, enter the following command:

```
/usr/opensv/netbackup/bin/nblu_registration -r
```

- 11 If you moved the NBDB files from their default installation location, you must delete these files manually as follows:

- Navigate to the following directory where the NBDB files reside:
`/usr/opensv/db/data`
- Open the `vxdbms.conf` file.
 This file contains a list of the database-related files and the path for each file.
- Delete each of the database-related files.

12 If NetBackup Fibre Transport is supported and enabled on the server, remove the associated files with the following command:

```
/usr/opensv/netbackup/bin/admincmd/nbftsrv_config -d
```

13 For the clients that support PureDisk, remove all PureDisk files with the following command:

```
/opt/pdag/bin/uninstall.sh
```

14 For the clients that support MSDP, remove all MSDP files with the following command:

```
/opt/pdde/pddeuninstall.sh -basedir /usr/opensv/pdde/ -ostdir  

/usr/opensv/lib/ost/plugins/ -forceclean
```

Note: Be aware the preceding command is a single command which takes three parameters (`basedir`, `ostdir`, and `forceclean`), and two directory parameters take paths as input.

15 To remove the NetBackup server package, run the following command:

AIX `installp -u SYMCnetbp`

HP-UX `swremove SYMCnetbp`

Linux `rpm -e SYMCnetbp`

Solaris `pkgrm SYMCnetbp`

- When the script asks if you want to remove the installed package `SYMCnetbp`, enter **y** and press **Enter**.
- When the script asks if you want to continue with the package removal using superuser permission, enter **y** and press **Enter**.

- 16** Remove the NetBackup-Java Display Console by using the appropriate native command as follows:

AIX	<code>installp -u SYMCnbjava</code>
HP-UX	<code>swremove SYMCnbjava</code>
Linux	<code>rpm -e SYMCnbjava</code>
Solaris	<code>pkgrm SYMCnbjava</code>

- 17** Remove the NetBackup Java Runtime Environment by using the appropriate native command as follows:

AIX	<code>installp -u SYMCnbjre</code>
HP-UX	<code>swremove SYMCnbjre</code>
Linux	<code>rpm -e SYMCnbjre</code>
Solaris	<code>pkgrm SYMCnbjre</code>

- 18** Remove the NetBackup client by using the appropriate native command as follows:

AIX	<code>installp -u SYMCnbclt</code>
HP-UX	<code>swremove SYMCnbclt</code>
Linux	<code>rpm -e SYMCnbclt</code>
Solaris	<code>pkgrm SYMCnbclt</code>

- 19** Remove PBX with the appropriate native command as follows:

Note: Remember, you should not remove PBX if your server uses other Symantec software products that require PBX to run.

AIX	<code>installp -u VRTSspb</code>
HP-UX	<code>swremove VRTSspb</code>
Linux	<code>rpm -e VRTSspb</code>
Solaris	<code>pkgrm VRTSspb</code>

20 To remove the `/usr/opensv` directory, select one of the following methods:

Warning: The `rm -f /usr/opensv` command also removes any add-on products that are installed on the computer where you perform this command.

- If `/usr/opensv` is the actual directory, run the following command:

```
rm -rf /usr/opensv
```

- If `/usr/opensv` is a symbolic link to that directory, run the following commands:

```
cd /usr/opensv
pwd
ls
```

Warning: Before you continue, make sure that you are at the correct location and verify that the subdirectories are what you expect them to be. To help prevent removing the wrong directories, the previous commands verify your current location and list the files in that directory. After you verify the directory location and its contents, remove the directory with the next commands.

```
rm -rf *
cd /
rm -f /usr/opensv
```

Note: Depending on your operating system, you may need to use the `rmdir` command to remove the `/usr/opensv` directory.

```
rmdir /usr/opensv
```

21 For Linux systems only:

If you modified the startup and the shutdown scripts, run the following command:

```
/sbin/chkconfig --del netbackup
```

See [“About NetBackup startup and shutdown scripts”](#) on page 114.

22 Remove the following startup scripts:

On AIX systems: `/etc/rc.netbackup.aix`

On HP-UX systems: `/sbin/init.d/netbackup`
`/sbin/rc1.d/K001netbackup`
`/sbin/rc2.d/S777netbackup`

On Linux Debian systems: `/etc.init.d/netbackup`
`/etc/rc0.d/K01netbackup`
`/etc/rc1.d/K01netbackup`
`/etc/rc2.d/S95netbackup`

On Linux Red Hat systems: `/etc/rc.d/init.d/netbackup`
`/etc/rc.d/rc0.d/K01netbackup`
`/etc/rc.d/rc1.d/K01netbackup`
`/etc/rc.d/rc2.d/S77netbackup`
`/etc/rc.d/rc3.d/S77netbackup`
`/etc/rc.d/rc5.d/S77netbackup`
`/etc/rc.d/rc6.d/K01netbackup`

The following startup scripts appear only if NetBackup Fiber Transport was enabled on the server:

`/etc/rc.d/init.d/nbftserver`
`/etc/rc.d/rc0.d/K03nbftserver`
`/etc/rc.d/rc1.d/K03nbftserver`
`/etc/rc.d/rc2.d/S21nbftserver`
`/etc/rc.d/rc3.d/S21nbftserver`
`/etc/rc.d/rc5.d/S21nbftserver`
`/etc/rc.d/rc6.d/K03nbftserver`

On Linux SUSE systems: `/etc/init.d/netbackup`
`/etc/init.d/rc0.d/K01netbackup`
`/etc/init.d/rc2.d/S77netbackup`
`/etc/init.d/rc3.d/S77netbackup`
`/etc/init.d/rc5.d/S77netbackup`
`/etc/init.d/rc6.d/K01netbackup`

The following startup scripts appear only if NetBackup Fiber Transport was enabled on the server:

`/etc/init.d/nbftserver`
`/etc/init.d/rc2.d/K01nbftserver`
`/etc/init.d/rc2.d/S05nbftserver`
`/etc/init.d/rc3.d/K01nbftserver`
`/etc/init.d/rc3.d/S05nbftserver`
`/etc/init.d/rc5.d/K01nbftserver`
`/etc/init.d/rc5.d/S05nbftserver`

On other servers: `/etc/init.d/netbackup`
`/etc/rc0.d/K01netbackup`
`/etc/rc1.d/K01netbackup`
`/etc/rc2.d/S77netbackup`

The following startup scripts appear only if NetBackup Fiber Transport was enabled on the server:

`/etc/init.d/nbftserver`
`/etc/rc0.d/K03nbftserver`
`/etc/rc1.d/K03nbftserver`
`/etc/rc2.d/S21nbftserver`

23 For AIX systems only:

- In the `/etc/inittab` file, remove the following NetBackup entry:

`/etc/rc.netbackup.aix`

- In the `/etc/rc.shutdown` file, remove the following line:

`/etc/rc.netbackup.aix stop`

24 Remove Symantec LiveUpdate components as follows:

- If NetBackup is the only Symantec product that currently uses LiveUpdate, run the following command:

`/opt/Symantec/LiveUpdate/uninstall.sh -a`

- If LiveUpdate is the only product installed in the `/opt/Symantec` directory, remove the following files:

```
rm -f /etc/Symantec.conf
rm -f /etc/Product.Catalog.JavaLiveUpdate
```

- 25 To remove the NetBackup-Java application state data for the root account, run the appropriate command as follows:

Warning: Do not insert a space between the slash character (/) and the period or the dot character (.) of `/.veritas`. A space between these characters removes all of your files from the root level and beyond.

- To remove the NetBackup-Java application state data for the root account for all releases, run the following command:

```
/bin/rm -rf /.veritas
```

- To remove the NetBackup-Java application state data for the root account for a specific release, run the following command:

```
/bin/rm -rf /.veritas/java/<version>
```

Where `<version>` is the six-digit NetBackup version number. For example, NetBackup version 7.7 with no upgrades applied would be entered as **770000**.

- 26 Inform NetBackup-Java users that they can remove their `$HOME/.veritas` directory.

The `$HOME/.veritas` and the `$HOME/.veritas/java` directories contain application state information, that is saved when the user exits NetBackup-Java applications. The saved information includes table column order and size. The process removes this directory for the root user only.

The common subdirectory in `$HOME/.veritas/java/.userPrefs/vrts` can be removed.

- 27 If you enabled NetBackup Access Control, NetBackup placed several files on clients and servers. These files can be divided into the following categories:

NetBackup application temporary files	These files are removed with NetBackup.
---------------------------------------	---

Individual user (cache) files These cache files reside in the `$HOME/.vxss` directory. Inform all users that they can remove this directory.

Files are generated in the `/.vxss` directory by a Single Sign-On operation of the NetBackup Administration Console on the host where the console runs. The NetBackup Administration Console cleans these files when an exit function is performed, so the directory does not always contain temporary files. However, if a system crash were to occur, any files in the directory may be left behind. With the console shutdown, you can delete these files safely with no data loss.

NetBackup also creates cached certificates for client and server NetBackup applications. These files reside within the `/.vxss` directory. These files typically have a name that is consistent with a DNS entry for a network interface, as in `machine.company.com`. Example directory entries are as follows:

```
/usr/opensv/var/vxss/credentials/machine.company.com  
  
/usr/opensv/var/vxss/credentials/dhcp
```

These files are created with the command `bpnbat -LoginMachine`. If you plan to reinstall NetBackup on the same computer at a later date, do one of the following:

- Preserve the certificates in the `vxss/credentials` directory.
- If you do not preserve the certificates, you must provide the computer identity password as originally set on the Root+AB broker. As an alternative, you can reset the password on the Root+AB broker when you reinstall.

For more information on Root+AB brokers, see the *NetBackup Security and Encryption Guide*.

<http://www.symantec.com/docs/DOC5332>

For more information on NetBackup Access Control and how to remove it, see the *NetBackup Security and Encryption Guide*.

<http://www.symantec.com/docs/DOC5332>

About NetBackup server software removal on Windows systems

When you remove NetBackup server software, the process deletes the `VERITAS/NetBackup` directories from the server.

You can remove NetBackup server software in the following ways:

- Remove server software, configuration, and catalog information.
- Remove server software and save NetBackup configuration and catalog information.

If you intend to reinstall NetBackup, use this procedure to save the configuration, catalog, and log file information before you remove NetBackup.

Note: After an uninstall, some registry and some directory information remain on a Windows computer. This behavior is by design, as these files may be in use by either the NetBackup Authentication Service or the NetBackup Authorization Service.

See [“Removing NetBackup server software on Windows systems”](#) on page 137.

Removing NetBackup server software on Windows systems

Use the following procedure to remove NetBackup server software and NetBackup configuration and catalog information.

To remove NetBackup server software and NetBackup configuration and catalog information

- 1 If the NetBackup Administration Console is open, close it.
If a console session is open when you try to remove NetBackup, a failure may occur that forces you to restart this procedure.
- 2 Select **Start > Settings > Control Panel**.
- 3 On the **Control Panel** window, for Windows 2008 and later, click **Programs and Features**.
- 4 On the **Currently Installed Programs** list, click **Symantec NetBackup**.

5 Click **Remove**.

For Windows 2008/Vista and later systems, after you click **Yes** to continue, another dialog box appears to inform you that PBX is still running.

Symantec recommends that you click **Do not close applications. (A reboot will be required.)** to continue with NetBackup removal. PBX is stopped and restarted automatically as needed for removal.

6 Remove the NetBackup deduplication user directory as follows:

In the **Documents and Settings** directory, delete the **purediskbuser** directory.

Use the following procedure to remove NetBackup server software and save NetBackup configuration and catalog information.

To remove NetBackup server software and save NetBackup configuration and catalog information

1 If the NetBackup Administration Console is open, close it.

If a console session is open when you try to remove NetBackup, a failure may occur that forces you to restart this procedure.

2 Select **Start > Settings > Control Panel**.

3 On the **Control Panel** window, for Windows 2008 and later, click **Programs and Features**.

4 In the **Currently Installed Programs** list, click **Symantec NetBackup** .

5 Click **Change**. This action lets you modify, repair, or remove NetBackup.

6 On the **Program Maintenance** dialog box, select **Remove**.

7 Clear the check mark next to **Remove all NetBackup Configuration, Catalog, and Log files** to disable this function. (The box is checked by default.)

8 Click **Next**.

9 If you enabled NetBackup Access Control, NetBackup placed several files on clients and servers. These files can be divided into the following categories:

NetBackup application temporary files	These files are removed with NetBackup.
---------------------------------------	---

Individual user (cache) files User cache files exist in their home directories, as follows:

```
user\Local Settings\Application
Data\VERITAS\NetBackup
```

Files are generated in the `\NetBackup` directory by a Single Sign-On operation of the NetBackup Administration Console on the host where the console runs. The NetBackup Administration Console cleans these files when an exit function is performed, so the directory does not always contain temporary files. If a system crash were to occur, however, any files in the directory may be left behind. With the console shutdown, you can delete these files safely with no data loss.

NetBackup also creates cached certificates for client and server NetBackup applications. These files reside within the `\NetBackup` directory. These files typically have a name that is consistent with a DNS entry for a network interface, such as `machine.company.com`. Example directory entries are as follows:

```
user\Local Settings\Application
Data\VERITAS\NetBackup\pc.comp.com

user\Local Settings\Application
Data\VERITAS\NetBackup\dhcp
```

These files are created with the command `bpnbat -LoginMachine`. If you plan to reinstall NetBackup on the same computer at a later date, do one of the following:

- Preserve the certificates in the `\NetBackup` directory.
- If you do not preserve the certificates, you must provide the computer identity password as originally set on the Root+AB broker. As an alternative, you can reset the password on the Root+AB broker when you reinstall. See the *NetBackup Security and Encryption Guide*.
<http://www.symantec.com/docs/DOC5332>

- 10 Remove the NetBackup deduplication user directory as follows:

Note: This step is necessary only if you upgraded to version 7.7.1 from a previous or earlier version of NetBackup.

In the **Documents and Settings** directory, delete the `purediskbuser` directory.

Removing NetBackup server software in a clustered environment

The following steps refer you to other documentation when you remove NetBackup software from clustered computers.

To remove NetBackup from a clustered environment

- 1 Follow the instructions in your cluster documentation for removing a group.
- 2 Remove NetBackup from each node in the cluster.

See [“To remove NetBackup server software and NetBackup configuration and catalog information”](#) on page 137.

No method exists to remove NetBackup from multiple nodes at the same time.

Removing NetBackup LiveUpdate from Windows systems

NetBackup LiveUpdate and Symantec LiveUpdate share the same LiveUpdate agent. When you remove LiveUpdate, you can no longer distribute NetBackup updates automatically or other Symantec product updates.

Before you remove LiveUpdate, make sure that no other installed Symantec products use LiveUpdate.

Use the following procedure to remove LiveUpdate files on Windows systems.

To remove NetBackup LiveUpdate on Windows systems

- 1 Select **Start > Control Panel**.
- 2 On the **Control Panel** window, do one of the following:
 - For Windows XP and earlier, click **Add/Remove Programs**.
 - For Windows Vista/2008 and later, click **Programs and Features**.
- 3 Click on **LiveUpdate** and select **Remove**.

About removal of the Java Console state data from Windows servers and Windows clients

The NetBackup Java Console stores state data on a per-user basis. This information includes user preferences, toolbar locations, and related settings. After you uninstall the NetBackup Java Console, remove the state data by deleting the following folder:

`USERPROFILE_DIR\Veritas\Java\JAVA_VERSION`

- For roaming user profiles, `USERPROFILE_DIR` is `%APPDATA%`.
- For local user profiles on Windows XP, and earlier, `USERPROFILE_DIR` is `%USERPROFILE%\Local Settings`.
- For local user profiles on Windows 2008/Vista, and later, `USERPROFILE_DIR` is `%LOCALAPPDATA%`.
- `JAVA_VERSION` is a six-digit NetBackup version number. For example, NetBackup version 7.5 with no upgrades applied would be `750000`.

Example:

On a Windows 2008 system with the 7.7 NetBackup Java Console previously installed, and a local user profile policy, the Java Console state folder exists at `%LOCALAPPDATA%\Veritas\Java\770000`.

Removing NetBackup client software

This chapter includes the following topics:

- [About NetBackup software removal on UNIX/Linux clients](#)
- [Removing NetBackup from UNIX/Linux clients](#)
- [Removing NetBackup Windows client software](#)

About NetBackup software removal on UNIX/Linux clients

Use the following guidelines when you remove NetBackup from UNIX/Linux clients:

When you remove NetBackup client software, PBX is not removed. You must remove PBX manually. The client software removal procedure in this document includes a step that describes how to perform this task.

Warning: Do not remove PBX if your client uses other Symantec software products that require PBX to run.

Removing NetBackup from UNIX/Linux clients

Use the following procedure to remove all NetBackup client software components from a UNIX/Linux client.

To remove NetBackup software from a UNIX/Linux client

- 1 Log in to the client system as the root user.
- 2 Stop the NetBackup daemons by entering the following command:

```
/usr/opensv/netbackup/bin/bp.kill_all
```

- 3 Identify any installed add-on products by using the following command:

AIX	lslpp -L
HP-UX	swlist
Linux	rpm -qa
Solaris	pkginfo

Three add-on products can be installed on the client. They are:

```
SYMCfrnbclt  

SYMCjanbclt  

SYMCzhnbclt
```

Remove any add-on products found.

- 4 To unregister NetBackup from the VxUL master configuration that is stored in the `/etc/vx/vrtslog.conf` file, run the following command:

```
/usr/opensv/netbackup/bin/vxlogcfg -r -p 51216
```

The `-p` option specifies the product ID, which is 51216 for NetBackup.

- 5 To unregister all NetBackup products with LiveUpdate, enter the following command:

```
/usr/opensv/netbackup/bin/nblu_registration -r
```

- 6 For the clients that support the PureDisk agent, remove all PureDisk files with the following command:

```
/opt/pdde/pddeuninstall.sh -forceclean
```

- 7** For the clients that support the NetBackup-Java Display Console, remove the console with the appropriate command as follows:

AIX	<code>installp -u SYMCnbjava</code>
HP-UX	<code>swremove SYMCnbjava</code>
Linux	<code>rpm -e SYMCnbjava</code>
Solaris	<code>pkgrm SYMCnbjava</code>

- 8** For the clients that support the NetBackup Java Runtime Environment (JRE), remove JRE with the appropriate command as follows:

AIX	<code>installp -u SYMCnbjre</code>
HP-UX	<code>swremove SYMCnbjre</code>
Linux	<code>rpm -e SYMCnbjre</code>
Solaris	<code>pkgrm SYMCnbjre</code>

- 9** For native package clients, remove the NetBackup client by using the appropriate commands as follows:

AIX	<code>installp -u SYMCnbclt</code>
HP-UX	<code>swremove SYMCnbclt</code>
Linux	<code>rpm -e SYMCnbclt</code>
Solaris	<code>pkgrm SYMCnbclt</code>

10 Remove PBX with the appropriate native command as follows:

Note: Do not remove PBX if your client uses other Symantec software products that require PBX to run.

AIX	<code>installp -u VRTSspb</code>
Debian	<code>/opt/VRTSspb/bin/vxpbx_exchanged stop</code> <code>rm -rf /opt/VRTSspb</code> <code>rm -rf /etc/vx/VxICS</code>
FreeBSD	<code>/opt/VRTSspb/bin/vxpbx_exchanged stop</code> <code>rm -rf /opt/VRTSspb</code> <code>rm -rf /etc/vx/VxICS</code> <code>rm -r /usr/share/man/man1/pbxcfg.1</code>
HP-UX	<code>swremove VRTSspb</code>
Linux	<code>rpm -e VRTSspb</code>
Macintosh OS X	<code>/opt/VRTSspb/bin/vxpbx_exchanged stop</code> <code>rm -r /Library/Receipts/VRTSspbApp.pkg</code> <code>rm -r /opt/VRTSspb</code> <code>rm -r /etc/vx/VxICS</code> <code>rm -r /usr/share/man/man1/pbxcfg.1</code> <code>rm -r /Library/StartupItems/vxpbx_exchanged</code>
Solaris	<code>pkgrm VRTSspb</code>

11 For all clients, navigate to the `/usr/openv` directory and proceed as follows:

Warning: The `rm -f /usr/openv` command also removes any add-on products that are installed on this computer.

- If `/usr/openv` is the actual directory, run the following command:
`rm -rf /usr/openv`
- If `/usr/openv` is a symbolic link to that directory, run the following commands:
`cd /usr/openv`

```
pwd  
ls
```

Warning: Before you continue, make sure that you are at the correct location and verify that the subdirectories are what you expect them to be. To help prevent removing the wrong directories, the previous commands verify your current location and list the files in that directory. After you verify the directory location and its contents, remove the directory with the next commands.

```
rm -rf *  
cd /  
rm -f /usr/opensv
```

12 For Linux systems only:

If you modified the startup and the shutdown scripts, run the following command:

```
/sbin/chkconfig --del netbackup
```

See [“About NetBackup startup and shutdown scripts”](#) on page 114.

13 Remove the following startup scripts:

AIX

`/etc/rc.netbackup.aix`

FreeBSD

`/usr/local/etc/netbackup`

`/usr/local/etc/rc.d/S77netbackup.sh`

HP-UX

`/sbin/init.d/netbackup`

`/sbin/rc1.d/K001netbackup`

`/sbin/rc2.d/S777netbackup`

Linux Debian

`/etc.init.d/netbackup`

`/etc/rc0.d/K01netbackup`

`/etc/rc1.d/K01netbackup`

`/etc/rc2.d/S95netbackup`

Linux Red Hat

`/etc/rc.d/init.d/netbackup`

`/etc/rc.d/rc0.d/K01netbackup`

`/etc/rc.d/rc1.d/K01netbackup`

`/etc/rc.d/rc2.d/S77netbackup`

`/etc/rc.d/rc3.d/S77netbackup`

`/etc/rc.d/rc5.d/S77netbackup`

`/etc/rc.d/rc6.d/K01netbackup`

Linux SUSE

`/etc/init.d/netbackup`

`/etc/init.d/rc0.d/K01netbackup`

`/etc/init.d/rc2.d/S77netbackup`

`/etc/init.d/rc3.d/S77netbackup`

`/etc/init.d/rc5.d/S77netbackup`

`/etc/init.d/rc6.d/K01netbackup`

Macintosh OS X

`/Library/StartupItems/netbackup/Resources/netbackup`

`/Library/StartupItems/netbackup/StartupParameters.plist`

`/Library/StartupItems/netbackup/netbackup`

Other clients

```
/etc/init.d/netbackup
/etc/rc0.d/K01netbackup
/etc/rc1.d/K01netbackup
/etc/rc2.d/S77netbackup
```

14 For AIX systems only:

- In the `/etc/inittab` file, remove the following NetBackup entry:
`/etc/rc.netbackup.aix`
- In the `/etc/rc.shutdown` file, remove the following line:
`/etc/rc.netbackup.aix stop`

15 Remove Symantec LiveUpdate components as follows:

- First, examine the following file to see if NetBackup is the only product that uses LiveUpdate:
`/etc/Product.Catalog.JavaLiveUpdate`
- If no entries in the file contain the string NetBackup, run the following commands:
`/opt/Symantec/LiveUpdate/uninstall.sh -a`
`rm -f /etc/Symantec.conf`

Note: Before you remove the following product catalog file, make sure that it is empty. The empty file size is equal to 0 bytes. If the product catalog file is not empty, do not remove it because other Symantec products still require it.

```
rm -f /etc/Product.Catalog.JavaLiveUpdate
```

16 To remove the NetBackup-Java application state data for the root account, run the appropriate command as follows:

Warning: Do not insert a space between the slash character (/) and the period or the dot character (.) of `/.veritas`. A space between these characters removes all of your files from the root level and beyond.

- To remove the NetBackup-Java application state data for the root account for all releases, run the following command:
`/bin/rm -rf /.veritas`

Reference

This chapter includes the following topics:

- [About the NetBackup Java Runtime Environment](#)
- [Using NetApp disk arrays with Replication Director](#)
- [Security updates to the NetBackup database](#)

About the NetBackup Java Runtime Environment

When you install NetBackup server software, a customized version of the Java Runtime Environment (JRE) is installed. NetBackup also installs this customized version of the JRE when you install the Remote Administration Console. You do not need to install or update this JRE separately. You can only update this version of the JRE through NetBackup maintenance updates. You may have additional versions of the JRE installed on your system for different applications. The NetBackup JRE does not interfere with these other installations. The NetBackup JRE does not provide integration with web browsers and does not allow Java Applets or Web Start to run. For that reason, the NetBackup JRE cannot be used in a browser-based attack that uses Java Applet or Web Start vulnerabilities.

For more information, see TECH50711.

<http://www.symantec.com/docs/TECH50711>

Using NetApp disk arrays with Replication Director

Replication Director can replicate snapshots on a NetApp disk array in two different situations:

- In non-cluster mode: 7-mode is used to replicate snapshots on NAS and SAN. The plug-in must be installed on the OnCommand Unified Manager (OCUM) server ([Figure 11-1](#)).

- In cluster-mode: Clustered Data ONTAP (cDOT) is used to replicate snapshots between storage virtual machines (SVMs or vServers). Support is for NAS only. The plug-in must be installed on either a Windows or a Linux computer other than the OCUM server, the master server, or any media servers (Figure 11-2).

Both modes support the same topologies.

Table 11-1 describes the association between NetBackup versions and the NetApp plug-ins.

Table 11-1 Version compatibility

NetBackup version	NetApp plug-in version	Description	Ratio of master server to OCUM server	Supported policy types
7.7	1.1	Provides 7-mode support for all NetBackup 7.7 Replication Director features.	One master server supports many OCUM servers. The plug-in must be installed on the OnCommand Unified Manager (OCUM) server.	MS-Windows, Standard, NDMP, VMware, Oracle
	2.0	Provides cDOT support.	One master server supports many OCUM servers. The plug-in must be installed on either a Windows or a Linux computer other than the OCUM server, the master server, or any media servers.	MS-Windows, Standard, NDMP, VMware, Oracle
7.6	1.1	NetApp Data ONTAP 7-Mode support for all of NetBackup 7.6 Replication Director features.	One master server to many OCUM servers	MS-Windows, Standard, NDMP, VMware, Oracle

Note: You must upgrade the entire NetBackup environment before upgrading the plug-in. Upgrade all master servers, media servers, clients, and any hosts which communicate with the plug-in.

Figure 11-1 Communication between NetBackup and the NBUPlugin for 7-mode





Figure 11-2 Communication between NetBackup and the NBUPlugin for Clustered Data ONTAP



Determining the version of the plug-in

To determine the NBUPlugin version, look for the following version file on the system where the NBUPlugin is installed:

On Windows: `Install_path\Program Files\Netapp\NBUPlugin\version.txt`

On UNIX: `/usr/NetApp/NBUPlugin/version.txt`

The contents of the file lists the product name, the build date, and the NBUPlugin version. If more than one plug-in is installed, both are listed.

Upgrading the plug-in

If upgrading the NetApp Plug-in for Symantec NetBackup, make sure that all storage lifecycle policy jobs that use the old plug-in are complete before upgrading.

To determine whether all of the jobs that are associated with a storage lifecycle policy are complete, in process, or not started, use the following command:

On Windows: C:\Program

```
Files\VERITAS\NetBackup\bin\admincmd>nbstlutil.exe stlilist -U
```

On UNIX: /usr/openv/netbackup/bin/admincmd/nbstlutil stlilist -U

Security updates to the NetBackup database

As a part of security changes in NetBackup, Symantec may make changes to your NetBackup (NBDB) database password. If you changed the password on the NetBackup database from the default value, no changes to the password are made. Any existing NetBackup databases which still have the default password are updated with a new, randomly generated password. All new installations of NetBackup have a randomly generated password assigned to the NetBackup database for improved security. This password is not provided to the user during installation or upgrade. You can use the `nbdb_admin` command to change this randomly generated password. See the *Symantec NetBackup Commands Reference Guide* for more information about the `nbdb_admin` command.

Index

A

- about
 - Backup Policy Wizard 123
 - client installation 85
 - client installation on Linux 97
 - client installation on UNIX 97
 - client installation on Windows 86
 - license key entry 26
 - Linux client installation methods 99
 - mounting NetBackup media 37
 - NetBackup 7.x Upgrade Portal 125
 - NetBackup catalog backup configuration 122
 - NetBackup Linux client removal 142
 - NetBackup Remote Administration Console for Windows 78
 - NetBackup server configuration 116
 - NetBackup UNIX client removal 142
 - NetBackup-Java Administration Console 82
 - preinstall checker 22
 - push client software 49
 - remote installation methods for Linux clients 102
 - remote installation methods for UNIX clients 102
 - startup and shutdown scripts 114
 - storage device configuration 20
 - Symantec Operations Readiness Tools 11
 - the preinstallation Environment Checker 56
 - UNIX client installation methods 99
 - Windows client installation methods 86
 - Windows client system requirements 86
- about NetBackup removal
 - on UNIX systems 127
- access control
 - remove files 139
- add remote servers
 - to administer from NetBackup Remote Administration Console 81
- add-on products
 - install 51
- adding Linux clients 108
- adding UNIX clients 108

- administer from NetBackup Remote Administration Console
 - add remote servers 81
- authentication certificates. *See* security certificates

B

- backup
 - online, hot catalog 122
- backup policies
 - guidelines for creating 123
- backup policy
 - backup types 123
 - create 123
- Backup Policy Wizard
 - about 123
- backup types
 - backup policy 123
- barcode rules
 - cleaning media 122
- bp.conf file
 - installation script 36
- bpplclients command 112
 - create client list 112

C

- catalog backup configuration
 - NetBackup wizards 122
- certificates. *See* security certificates
- cleaning media
 - barcode rules 122
- client installation
 - about 85
 - methods for Linux 99
 - methods for UNIX 99
 - methods for Windows 86
- client installation methods
 - for remote Linux clients 102
 - for remote UNIX clients 102
- client installation on Linux
 - about 97

- client installation on UNIX
 - about 97
 - client installation on Windows
 - about 86
 - client software
 - install locally on Windows 89
 - client type software
 - install on master server 50
 - client_config script 104, 107
 - clients
 - about remote installation methods for Linux clients 102
 - about remote installation methods for UNIX clients 102
 - adding after initial install 108
 - loading onto server 108
 - pushing software to 108
 - upgrading after server upgrades 110
 - cluster
 - private network 71
 - Cluster Administrator console
 - verify Windows cluster installation or upgrade 74
 - cluster group
 - configuration 71
 - install new 70
 - cluster group name 70
 - cluster installation and upgrade
 - requirements 59
 - cluster installations
 - post-installation tasks 74
 - cluster installations or upgrades
 - verify Windows 74
 - commands
 - bpplclients 112
 - compatibility
 - license keys 26
 - NetBackup-Java 99
 - configuration
 - master and media servers 116
 - NetBackup servers 116
 - configuration guidelines
 - NetBackup Enterprise servers 116
 - configure
 - cluster group 71
 - NetBackup catalog backup 122
 - NetBackup storage devices 119
 - NetBackup volumes 121
 - Windows client 96
 - configure catalog backup
 - guidelines 122
 - configure storage devices
 - for the operating system 20
 - configure window manager
 - for Java interface 51
 - NetBackup-Java compatible platforms 51
 - continue installation
 - after master server installation 45
 - create
 - backup policy 123
 - create client list
 - bpplclients command 112
- ## D
- define
 - storage units 121
 - device configuration
 - guidelines 120
 - NetBackup wizards 119
 - Domain Name Service (DNS) 33
- ## E
- Environment Checker
 - about 56
 - run before installation 57
 - ESD images
 - for NetBackup 19
- ## F
- frequently asked questions
 - license keys 28
 - ftp method
 - install UNIX client 104
 - remote UNIX client installation 104
- ## G
- general requirements
 - UNIX server installation 33
 - Getting Started
 - NetBackup wizards 116
 - guidelines
 - configure catalog backup 122
 - device configuration 120
 - for creating backup policies 123
 - robot inventory 122
 - standalone drive inventory 122

- gunzip command
 - required for installation 33
 - UNIX client installation 98
- gzip command
 - required for installation 33
 - UNIX client installation 98

H

- hosts file 33
- how to install
 - sequence for new installations 21
- how to start
 - NetBackup Administration Console 118

I

- inetd.conf file
 - installation script 36
- install
 - add-on products 51
 - Java Windows Administration Console 82
 - NetBackup Remote Administration Console 78
 - new cluster group 70
- install locally
 - client software on Windows 89
- install locally on Windows
 - server software 61
- install multiple versions of NetBackup Administration Console
 - restrictions and guidelines 83
- install multiple versions on Windows
 - NetBackup-Java Administration Console 83
- install NetBackup clients
 - locally 100
- install on clustered Windows environments
 - server software 61
- install on master server
 - client type software 50
- install remotely
 - Windows client software 89
- install remotely on Windows
 - server software 61
- install silently
 - Windows client 95
- install UNIX client
 - ftp method 104
 - rsh method 103
 - sftp method 107
 - ssh method 106

- install_client_files script 106–107
- installation
 - methods for Linux clients 99
 - methods for UNIX clients 99
 - methods for Windows clients 86
 - UNIX clients locally 100
- installation guidelines
 - HP-UX systems 35
 - Solaris systems 35
 - UNIX clusters 35
- installation restrictions
 - Windows client 86
- installation script
 - bp.conf file 36
 - inetd.conf file 36
 - server installation 36
 - services file 36
- inventory
 - robot 122
 - standalone drive 122
- IPv4 clusters 70
- IPv6 clusters 70

J

- Java Console
 - installing multiple versions 83
 - removing multiple versions 83
- Java interface
 - configure window manager 51
- Java Windows Administration Console
 - install 82

L

- license key entry
 - about 26
- license keys
 - compatibility 26
 - frequently asked questions 28
 - requirements 25
- Linux
 - mount NetBackup DVD 38
- Linux client
 - about removing PBX 142
- Linux client installation methods
 - about 99
- Linux clients
 - installation methods 99
 - remove NetBackup 142

- Linux systems
 - server installation requirements 32
- loading client types onto server 108
- local installation
 - UNIX client 99
 - Windows client 87

M

- master and media servers
 - configuration 116
 - master server
 - continue installation after 45
 - install client type software 50
 - software installation 39
 - media kit
 - description of contents 18
 - media server
 - software installation 45
 - methods
 - for Linux client installation 99
 - for UNIX client installation 99
 - for Windows client installation 86
 - mixed version support
 - NetBackup 7.x 11
 - mount DVD
 - NetBackup installation 37
 - mount NetBackup DVD
 - Linux 38
 - UNIX 38
- ## N
- NBUPlugin
 - determining the version 153
 - upgrading 154
 - NetBackup
 - ESD images 19
 - how to install 21
 - media kit contents 18
 - port numbers 55
 - NetBackup 7.x
 - mixed version support 11
 - NetBackup Access Control
 - remove files 135
 - NetBackup Administration Console 82
 - how to start 118
 - NetBackup catalog 54
 - NetBackup catalog backup configuration
 - about 122
 - NetBackup client software
 - add a UNIX client type 108
 - install locally 100
 - NetBackup DVDs 18
 - NetBackup Electronic Software Distribution (ESD)
 - images 18
 - NetBackup Enterprise servers
 - configuration guidelines 116
 - NetBackup installation
 - mount DVD 37
 - NetBackup LiveUpdate
 - remove from Windows systems 140
 - NetBackup media
 - about mounting 37
 - NetBackup media kit
 - about 18
 - NetBackup Product Improvement Program 23
 - NetBackup Remote Administration Console
 - configure server lists for 80
 - installation 78
 - NetBackup Remote Administration Console for Windows
 - about 78
 - NetBackup scripts
 - startup and shutdown 114
 - UNIX 114
 - NetBackup server configuration
 - about 116
 - NetBackup server software
 - about removal on UNIX 127
 - NetBackup servers
 - configuration 116
 - remove software 137
 - NetBackup storage devices
 - configure 119
 - NetBackup upgrades 125
 - NetBackup volumes
 - configure 121
 - NetBackup wizards
 - backup policy configuration 123
 - catalog backup configuration 122
 - device configuration 119
 - Getting Started 116
 - volume configuration 121
 - NetBackup-Java
 - compatibility 99
 - NetBackup-Java Administration Console
 - about 82
 - install multiple versions on Windows 83

- NetBackup-Java Administration Console (*continued*)
 - remove multiple versions on Windows 84
 - NetBackup-Java compatible platforms
 - configure window manager 51
 - Network Information Service (NIS) 33
 - new installations
 - sequence 21
 - NTFS partition 54, 88
- O**
- online, hot catalog
 - backup 122
 - operating system
 - configure storage devices for 20
- P**
- PBX
 - about removal from Linux clients 142
 - about removal from UNIX clients 142
 - remove 128
 - remove from non-Solaris 128
 - ping command 54
 - plug-ins
 - NetApp 151
 - upgrading from NetApp 154
 - post-installation tasks
 - cluster installations 74
 - preinstall checker
 - about 22
 - preinstallation
 - about the Environment Checker 56
 - running the Environment Checker 57
 - private network
 - cluster 71
 - public network 71
 - push client software
 - about 49
 - push installation
 - UNIX client 100
 - pushing client software 108
- R**
- recommended installation procedures
 - Symantec Operations Readiness Tools 12
 - recommended upgrade procedures
 - Symantec Operations Readiness Tools 16
 - remote
 - about installation methods for Linux clients 102
 - remote (*continued*)
 - about installation methods for UNIX clients 102
 - remote installation
 - about methods for Linux clients 102
 - about methods for UNIX clients 102
 - UNIX client 100
 - Windows client 88
 - remote UNIX client installation
 - ftp method 104
 - rsh method 103
 - sftp method 107
 - ssh method 106
 - remove
 - server software in clusters 140
 - Windows Java Console 141
 - Windows server software 137
 - remove files
 - access control 139
 - remove from Windows systems
 - NetBackup LiveUpdate 140
 - remove multiple versions on Windows
 - NetBackup-Java Administration Console 84
 - remove NetBackup
 - from UNIX servers 128
 - Linux clients 142
 - UNIX clients 142
 - remove NetBackup software
 - about Linux clients 142
 - about UNIX clients 142
 - Windows client 149
 - remove software
 - NetBackup servers 137
 - requirements
 - cluster installation and upgrade 59
 - license keys 25
 - requirements for server installation
 - Red Hat Linux 34
 - restrictions and guidelines
 - install multiple versions of NetBackup Administration Console 83
 - robot
 - inventory 122
 - robot inventory
 - guidelines 122
 - robot types
 - locate supported 21
 - rsh method
 - install UNIX client 103
 - remote UNIX client installation 103

S

- scripts
 - client_config 104, 107
 - install_client_files 106
 - install_client_files using ftp 104
 - install_client_files using sftp 107
 - install_client_files using ssh 106
- security certificates
 - about 23
 - for cloud storage 23
- sequence
 - for installations 21
- server configuration
 - Windows 2008 54
- server installation
 - installation script 36
 - requirements for Red Hat Linux 34
- server installation requirements
 - Linux systems 32
 - UNIX systems 32
 - Windows systems 53
- server lists
 - configure for NetBackup Remote Administration Console 80
- server software
 - install in clustered Windows environments 61
 - install locally on Windows 61
 - install remotely on Windows 61
 - remove in clusters 140
- server software removal
 - on UNIX systems 127
- servers
 - silent installation on Windows 75
- services file
 - installation script 36
- sftp method
 - install UNIX client 107
 - remote UNIX client installation 107
- Shared Storage Option (SSO)
 - storing device information 66
- silent installation on Windows
 - servers 75
- silent Installations
 - Windows client 88
- software installation
 - master server 39
 - media server 45

SORT

- Symantec Operations Readiness Tools 11–12, 16
- ssh method
 - install UNIX client 106
 - remote UNIX client installation 106
- standalone drive
 - inventory 122
- standalone drive inventory
 - guidelines 122
- startup and shutdown
 - NetBackup scripts 114
- startup and shutdown scripts
 - about 114
- storage device configuration
 - about 20
- storage units
 - define 121
- store device information
 - Shared Storage Option (SSO) 66
- subnet mask 70
- supported robot types
 - locate for this release 21
- Symantec Operations Readiness Tools (SORT)
 - about 11
 - recommended installation procedures 12
 - recommended upgrade procedures 16
- system requirements
 - Windows clients 86

U

- uninstall
 - Windows Java Console 141
 - Windows server software 137
- UNIX
 - mount NetBackup DVD 38
 - NetBackup scripts 114
- UNIX client
 - about removing PBX 142
 - local installation 99
 - push installation 100
 - remote installation 100
- UNIX client installation methods
 - about 99
- UNIX clients
 - installation methods 99
 - installing locally 100, 108
 - remove NetBackup 142

- UNIX server installation
 - general requirements 33
- UNIX servers
 - remove NetBackup from 128
- UNIX systems
 - server installation requirements 32
- upgrade clients
 - after upgrading servers 110
- upgrade portal
 - about NetBackup 7.x 125
- upgrade to NetBackup 7.x
 - about the upgrade portal 125
- user permissions
 - user-directed operations 86
 - Windows client 86
- user-directed operations
 - user permissions 86

V

- verify
 - Windows cluster installations or upgrades 74
- verify Windows cluster installation or upgrade
 - Cluster Administrator console 74
- versions, determining NetApp NBUPlugin 151
- virtual host name 71
- virtual IP address 70
- volume configuration
 - NetBackup wizards 121

W

- Windows
 - clustered install 61
 - local install 61
 - remote install 61
 - remove or uninstall Java Console 141
 - remove or uninstall server software 137
 - remove or uninstall software 137
 - silent install 75
 - verify cluster installation 74
- Windows 2008
 - server configuration 54
- Windows client
 - configure 96
 - install silently 95
 - installation restrictions 86
 - local installation 87
 - remote installation 88
 - remove NetBackup software 149

- Windows client (*continued*)
 - silent installation 88
 - user permissions 86
- Windows client installation methods
 - about 86
- Windows client software
 - install remotely 89
- Windows client system requirements
 - about 86
- Windows clients
 - installation methods 86
 - system requirements 86
- Windows systems
 - cluster installation and upgrade requirements 59
 - server installation requirements 53